



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'opendir.3'

\$ man opendir.3

OPENDIR(3)

Linux Programmer's Manual

OPENDIR(3)

NAME

opendir, fdopendir - open a directory

SYNOPSIS

```
#include <sys/types.h>
#include <dirent.h>
DIR *opendir(const char *name);
DIR *fdopendir(int fd);
```

Feature Test Macro Requirements for glibc (see `feature_test_macros(7)`):

`fdopendir()`:

Since glibc 2.10:

`_POSIX_C_SOURCE >= 200809L`

Before glibc 2.10:

`_GNU_SOURCE`

DESCRIPTION

The `opendir()` function opens a directory stream corresponding to the directory name, and returns a pointer to the directory stream. The stream is positioned at the first entry in the directory.

The `fdopendir()` function is like `opendir()`, but returns a directory stream for the directory referred to by the open file descriptor `fd`. After a successful call to `fdopendir()`, `fd` is used internally by the implementation, and should not otherwise be used by the application.

The `opendir()` and `fdopendir()` functions return a pointer to the directory stream. On error, `NULL` is returned, and `errno` is set appropriately.

ERRORS

EACCES Permission denied.

EBADF `fd` is not a valid file descriptor opened for reading.

EMFILE The per-process limit on the number of open file descriptors has been reached.

ENFILE The system-wide limit on the total number of open files has been reached.

ENOENT Directory does not exist, or name is an empty string.

ENOMEM Insufficient memory to complete the operation.

ENOTDIR

name is not a directory.

VERSIONS

`fdopendir()` is available in glibc since version 2.4.

ATTRIBUTES

For an explanation of the terms used in this section, see `attributes(7)`.

??

?Interface ? Attribute ? Value ?

??

?`opendir()`, `fdopendir()` ? Thread safety ? MT-Safe ?

??

CONFORMING TO

`opendir()` is present on SVr4, 4.3BSD, and specified in POSIX.1-2001. `fdopendir()` is specified in POSIX.1-2008.

NOTES

Filename entries can be read from a directory stream using `readdir(3)`.

The underlying file descriptor of the directory stream can be obtained using `dirfd(3)`.

The `opendir()` function sets the close-on-exec flag for the file descriptor underlying the `DIR *`. The `fdopendir()` function leaves the setting of the close-on-exec flag unchanged for the file descriptor, `fd`. POSIX.1-200x leaves it unspecified whether a successful call to `fdopendir()` will set the close-on-exec flag for the file descriptor, `fd`.

SEE ALSO

`open(2)`, `closedir(3)`, `dirfd(3)`, `readdir(3)`, `rewinddir(3)`, `scandir(3)`, `seekdir(3)`, `telldir(3)`

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

GNU

2017-09-15

OPENDIR(3)