



Full credit is given to the above companies including the OS that this PDF file was generated!

Linux Ubuntu 22.4.5 Manual Pages on command 'sntp.1'

\$ man sntp.1

SNTP(1) BSD General Commands Manual SNTP(1)

NAME

sntp ? standard Simple Network Time Protocol client program

SYNOPSIS

sntp [-flags] [-flag [value]] [--option-name[[:=]]value]] [hostname-or-IP ...]

DESCRIPTION

sntp can be used as an SNTP client to query a NTP or SNTP server and either display the time or set the local system's time (given suitable privilege). It can be run as an interactive command or from a cron job. NTP (the Network Time Protocol) and SNTP (the Simple Network Time Protocol) are defined and described by RFC 5905.

The default is to write the estimated correct local date and time (i.e. not UTC) to the standard output in a format like: '1996-10-15 20:17:25.123 (+0800) +4.567 +/- 0.089 [host] IP sN' where the '(+0800)' means that to get to UTC from the reported local time one must add 8 hours and 0 minutes, the '+4.567' indicates the local clock is 4.567 seconds behind the correct time (so 4.567 seconds must be added to the local clock to get it to be correct). Note that the number of decimals printed for this value will change based on the reported precision of the server. '+/-. 0.089' is the reported synchronization distance (in seconds), which represents the maximum error due to all causes. If the server does not report valid data needed to calculate the synchronization distance, this will be reported as '+/-. ?'. If the host is different from the IP, both will be displayed. Otherwise, only the IP is displayed. Finally, the stratum of the host is reported and the leap indicator is decoded and displayed.

OPTIONS

-4, --ipv4

Force IPv4 DNS name resolution. This option must not appear in combination with any of the following options: ipv6.

Force DNS resolution of the following host names on the command line to the IPv4 namespace.

-6, --ipv6

Force IPv6 DNS name resolution. This option must not appear in combination with any of the following options: ipv4.

Force DNS resolution of the following host names on the command line to the IPv6 namespace.

-a auth-keynumber, --authentication=auth-keynumber

Enable authentication with the key auth-keynumber. This option takes an integer number as its argument.

Enable authentication using the key specified in this option's argument. The argument of this option is the keyid, a number specified in the keyfile as this key's identifier. See the keyfile option (-k) for more details.

-b broadcast-address, --broadcast=broadcast-address

Listen to the address specified for broadcast time sync. This option may appear an unlimited number of times.

If specified sntp will listen to the specified address for NTP broadcasts.

The default maximum wait time can (and probably should) be modified with -t.

-c host-name, --concurrent=host-name

Concurrently query all IPs returned for host-name. This option may appear an unlimited number of times.

Requests from an NTP "client" to a "server" should never be sent more rapidly than one every 2 seconds. By default, any IPs returned as part of a DNS lookup are assumed to be for a single instance of ntpd, and therefore sntp will send queries to these IPs one after another, with a 2-second gap between each query.

The -c or --concurrent flag says that any IPs returned for the DNS lookup of the supplied host-name are on different machines, so we can send concurrent queries.

-d, --debug-level

Increase debug verbosity level. This option may appear an unlimited number of times.

-D number, --set-debug-level=number

Set the debug verbosity level. This option may appear an unlimited number of times. This option takes an integer number as its argument.

-g milliseconds, --gap=milliseconds

The gap (in milliseconds) between time requests. This option takes an integer number as its argument. The default milliseconds for this option is:

50

Since we're only going to use the first valid response we get and there is benefit to specifying a good number of servers to query, separate the queries we send out by the specified number of milliseconds.

-K file-name, --kod=file-name

KoD history filename. The default file-name for this option is:

/var/db/ntp-kod

Specifies the filename to be used for the persistent history of KoD responses received from servers. If the file does not exist, a warning message will be displayed. The file will not be created.

-k file-name, --keyfile=file-name

Look in this file for the key specified with -a. The default file-name for this option is:

/etc/ntp.keys

This option specifies the keyfile. sntp will search for the key specified with -a keyno in this file. See ntp.keys(5) for more information.

-l file-name, --logfile=file-name

Log to specified logfile.

This option causes the client to write log messages to the specified logfile.

-M number, --steplimit=number

Adjustments less than steplimit msec will be slewed. This option takes an integer number as its argument. The value of number is constrained to being: greater than or equal to 0

If the time adjustment is less than steplimit milliseconds, slew the amount

using adjtime(2). Otherwise, step the correction using settimofday(2). The default value is 0, which means all adjustments will be stepped. This is a feature, as different situations demand different values.

-o number, **--ntpversion=number**

Send int as our NTP protocol version. This option takes an integer number as its argument. The value of number is constrained to being:

in the range 0 through 7

The default number for this option is:

4

When sending requests to a remote server, tell them we are running NTP proto?

col version ntpversion .

-r, --usereservedport

Use the NTP Reserved Port (port 123).

Use port 123, which is reserved for NTP, for our network communications.

-S, --step

OK to 'step' the time with settimofday(2).

-s, --slew

OK to 'slew' the time with adjtime(2).

-t seconds, --timeout=seconds

The number of seconds to wait for responses. This option takes an integer number as its argument. The default seconds for this option is:

5

When waiting for a reply, sntp will wait the number of seconds specified before giving up. The default should be more than enough for a unicast response. If sntp is only waiting for a broadcast response a longer timeout is likely needed.

--wait, - Fl -no-wait

Wait for pending replies (if not setting the time). The no-wait form will disable the option. This option is enabled by default.

If we are not setting the time, wait for all pending responses.

-?, --help

Display usage information and exit.

-!, --more-help

Pass the extended usage information through a pager.

-> [cfgfile], --save-opts [=cfgfile]

Save the option state to cfgfile. The default is the last configuration file listed in the OPTION PRESETS section, below. The command will exit after updating the config file.

-< cfgfile, --load-opts=cfgfile, --no-load-opts

Load options from cfgfile. The no-load-opts form will disable the loading of earlier config/rc/ini files. --no-load-opts is handled early, out of order.

--version [{v|c|n}]

Output version of program and exit. The default mode is 'v', a simple version. The 'c' mode will print copyright information and 'n' will print the full copyright notice.

OPTION PRESETS

Any option that is not marked as not presettable may be preset by loading values from configuration ("RC" or ".INI") file(s) and values from environment variables named:

SNTP_<option-name> or SNTP

The environmental presets take precedence (are processed later than) the configuration files. The homerc files are "\$HOME", and ". ". If any of these are directories, then the file .ntpvc is searched for within those directories.

USAGE

sntp ntpserver.somewhere

is the simplest use of this program and can be run as an unprivileged command to check the current time and error in the local clock.

sntp -Ss -M 128 ntpserver.somewhere

With suitable privilege, run as a command or from a cron(8) job, sntp -Ss -M 128 ntpserver.somewhere will request the time from the server, and if that server reports that it is synchronized then if the offset adjustment is less than 128 milliseconds the correction will be slewed, and if the correction is more than 128 milliseconds the correction will be stepped.

sntp -S ntpserver.somewhere

With suitable privilege, run as a command or from a cron(8) job, sntp -S ntpserver.somewhere will set (step) the local clock from a synchronized specified server, like the (deprecated) ntpdate(8), or rdate(8) commands.

ENVIRONMENT

See OPTION PRESETS for configuration environment variables.

FILES

See OPTION PRESETS for configuration files.

EXIT STATUS

One of the following exit values will be returned:

0 (EXIT_SUCCESS)

Successful program execution.

1 (EXIT_FAILURE)

The operation failed or the command syntax was not valid.

66 (EX_NOINPUT)

A specified configuration file could not be loaded.

70 (EX_SOFTWARE)

libopts had an internal operational error. Please report it to auto?

gen-users@lists.sourceforge.net. Thank you.

AUTHORS

Johannes Maximilian Kuehn

Harlan Stenn

Dave Hart

COPYRIGHT

Copyright (C) 1992-2017 The University of Delaware and Network Time Foundation all rights reserved. This program is released under the terms of the NTP license, <<http://ntp.org/license>>.

BUGS

Please send bug reports to: <http://bugs.ntp.org>, bugs@ntp.org

NOTES

This manual page was AutoGen-erated from the sntp option definitions.

BSD

August 14 2018

BSD