



Rocky Enterprise Linux 9.2 Manual Pages on command 'Archive::Zip::MemberRead.3pm'

C:\>man Archive::Zip::MemberRead.3pm

Archive::Zip::MemberRead(3pmUser Contributed Perl DocumentatiArchive::Zip::MemberRead(3pm)

NAME

Archive::Zip::MemberRead - A wrapper that lets you read Zip archive members as if they were files.

SYNOPSIS

```
use Archive::Zip;
use Archive::Zip::MemberRead;
$zip = Archive::Zip->new("file.zip");
$fh = Archive::Zip::MemberRead->new($zip, "subdir/abc.txt");
while (defined($line = $fh->getline()))
{
    print $fh->input_line_number . " #: $line\n";
}

$read = $fh->read($buffer, 32*1024);
print "Read $read bytes as :$buffer:\n";
```

DESCRIPTION

The Archive::Zip::MemberRead module lets you read Zip archive member data just like you read data from files.

METHODS

Archive::Zip::Member::readFileHandle()

You can get a "Archive::Zip::MemberRead" from an archive member by calling "readFileHandle()":

```
my $member = $zip->memberNamed('abc/def.c');
my $fh = $member->readFileHandle();
while (defined($line = $fh->getline()))
{
    # ...
}
$fh->close();
```

Archive::Zip::MemberRead->new(\$zip, \$fileName)

Archive::Zip::MemberRead->new(\$zip, \$member)

Archive::Zip::MemberRead->new(\$member)

Construct a new Archive::Zip::MemberRead on the specified member.

```
my $fh = Archive::Zip::MemberRead->new($zip, 'fred.c')
```

setLineEnd(expr)

Set the line end character to use. This is set to `\n` by default except on Windows systems where it is set to `\r\n`. You will only need to set this on systems which are not Windows or Unix based and require a line end different from `\n`. This is a class method so call as

```
"Archive::Zip::MemberRead"->"setLineEnd($nl)"
```

rewind()

Rewinds an "Archive::Zip::MemberRead" so that you can read from it again starting at the beginning.

input_record_separator(expr)

If the argument is given, `input_record_separator` for this instance is set to it. The current setting (which may be the global `$/`) is always returned.

`input_line_number()`

Returns the current line number, but only if you're using `"getline()"`. Using `"read()"` will not update the line number.

`close()`

Closes the given file handle.

`buffer_size([$size])`

Gets or sets the buffer size used for reads. Default is the chunk size used by `Archive::Zip`.

`getline()`

Returns the next line from the currently open member. Makes sense only for text files. A read error is considered fatal enough to die. Returns `undef` on eof. All subsequent calls would return `undef`, unless a `rewind()` is called.

Note: The line returned has the `input_record_separator` (default: `newline`) removed.

`getline({ preserve_line_ending => 1 })`

Returns the next line including the line ending.

`read($buffer, $num_bytes_to_read)`

Simulates a normal `"read()"` system call. Returns the no. of bytes read.

`"undef"` on error, 0 on eof, e.g.:

```
$fh = Archive::Zip::MemberRead->new($zip, "sreeji/secrets.bin");
```

```
while (1)
```

```
{
```

```
  $read = $fh->read($buffer, 1024);
```

```
  die "FATAL ERROR reading my secrets !\n" if (!defined($read));
```

```
last if (!$read);  
# Do processing.  
....  
}
```

AUTHOR

Sreeji K. Das <sreeji_k@yahoo.com>

See Archive::Zip by Ned Konz without which this module does not make any sense!

Minor mods by Ned Konz.

COPYRIGHT

Copyright 2002 Sreeji K. Das.

This program is free software; you can redistribute it and/or modify it under the same terms as Perl itself.

perl v5.30.0

2020-02-27

Archive::Zip::MemberRead(3pm)