



## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'getfacl.1'***

**C:\>man getfacl.1**

GETFACL(1)                    Access Control Lists                    GETFACL(1)

### NAME

getfacl - get file access control lists

### SYNOPSIS

getfacl [-aceEsRLPtpndvh] file ...

getfacl [-aceEsRLPtpndvh] -

### DESCRIPTION

For each file, `getfacl` displays the file name, owner, the group, and the Access Control List (ACL). If a directory has a default ACL, `getfacl` also displays the default ACL. Non-directories cannot have default ACLs.

If `getfacl` is used on a file system that does not support ACLs, `getfacl` displays the access permissions defined by the traditional file mode permission bits.

The output format of `getfacl` is as follows:

```
1: # file: somedir/
2: # owner: lisa
3: # group: staff
4: # flags: -s-
5: user::rwx
6: user:joe:rwx      #effective:r-x
7: group::rwx       #effective:r-x
8: group:cool:r-x
9: mask::r-x
```

```
10: other::r-x
11: default:user::rwx
12: default:user:joe:rwx    #effective:r-x
13: default:group::r-x
14: default:mask::r-x
15: default:other::---
```

Lines 1--3 indicate the file name, owner, and owning group.

Line 4 indicates the setuid (s), setgid (s), and sticky (t) bits: either the letter representing the bit, or else a dash (-). This line is included if any of those bits is set and left out otherwise, so it will not be shown for most files. (See CONFORMANCE TO POSIX 1003.1e DRAFT STANDARD 17 below.)

Lines 5, 7 and 10 correspond to the user, group and other fields of the file mode permission bits. These three are called the base ACL entries. Lines 6 and 8 are named user and named group entries. Line 9 is the effective rights mask. This entry limits the effective rights granted to all groups and to named users. (The file owner and others permissions are not affected by the effective rights mask; all other entries are.) Lines 11--15 display the default ACL associated with this directory. Directories may have a default ACL. Regular files never have a default ACL.

The default behavior for `getfacl` is to display both the ACL and the default ACL, and to include an effective rights comment for lines where the rights of the entry differ from the effective rights.

If output is to a terminal, the effective rights comment is aligned to column 40.

Otherwise, a single tab character separates the ACL entry and the effective rights comment.

The ACL listings of multiple files are separated by blank lines. The output of `getfacl` can also be used as input to `setfacl`.

## PERMISSIONS

Processes with search access to a file (i.e., processes with read access to the containing directory of a file) are also granted read access to the file's ACLs. This is analogous to the permissions required for accessing the file mode.

## OPTIONS

`-a, --access`

Display the file access control list.

-d, --default

Display the default access control list.

-c, --omit-header

Do not display the comment header (the first three lines of each file's output).

-e, --all-effective

Print all effective rights comments, even if identical to the rights defined by the ACL entry.

-E, --no-effective

Do not print effective rights comments.

-s, --skip-base

Skip files that only have the base ACL entries (owner, group, others).

-R, --recursive

List the ACLs of all files and directories recursively.

-L, --logical

Logical walk, follow symbolic links to directories. The default behavior is to follow symbolic link arguments, and skip symbolic links encountered in subdirectories. Only effective in combination with -R.

-P, --physical

Physical walk, do not follow symbolic links to directories. This also skips symbolic link arguments. Only effective in combination with -R.

-t, --tabular

Use an alternative tabular output format. The ACL and the default ACL are displayed side by side. Permissions that are ineffective due to the ACL mask entry are displayed capitalized. The entry tag names for the ACL\_USER\_OBJ and ACL\_GROUP\_OBJ entries are also displayed in capital letters, which helps in spotting those entries.

-p, --absolute-names

Do not strip leading slash characters (/). The default behavior is to strip leading slash characters.

-n, --numeric

List numeric user and group IDs

-v, --version

Print the version of getfacl and exit.

-h, --help

Print help explaining the command line options.

-- End of command line options. All remaining parameters are interpreted as file names, even if they start with a dash character.

- If the file name parameter is a single dash character, getfacl reads a list of files from standard input.

#### CONFORMANCE TO POSIX 1003.1e DRAFT STANDARD 17

If the environment variable POSIXLY\_CORRECT is defined, the default behavior of getfacl changes in the following ways: Unless otherwise specified, only the ACL is printed. The default ACL is only printed if the -d option is given. If no command line parameter is given, getfacl behaves as if it was invoked as ``getfacl -". No flags comments indicating the setuid, setgid, and sticky bits are generated.

#### AUTHOR

Andreas Gruenbacher, <andreas.gruenbacher@gmail.com>.

Please send your bug reports and comments to the above address.

#### SEE ALSO

setfacl(1), acl(5)

May 2000

ACL File Utilities

GETFACL(1)