



Rocky Enterprise Linux 9.2 Manual Pages on command 'lvrename.8'

C:\>man lvrename.8

LVRENAME(8) System Manager's Manual LVRENAME(8)

NAME

lvrename - Rename a logical volume

SYNOPSIS

lvrename position_args

[option_args]

DESCRIPTION

lvrename renames an existing LV or a historical LV (see lvremove for historical LV information.)

USAGE

lvrename VG LV LV_new

[COMMON_OPTIONS]

lvrename LV LV_new

[COMMON_OPTIONS]

Common options for command:

[-A|--autobackup y|n]

[--noudevsync]

[--reportformat basic|json]

Common options for lvm:

[-d|--debug]

[-h|--help]

[-q|--quiet]

[-t|--test]
[-v|--verbose]
[-y|--yes]
[--commandprofile String]
[--config String]
[--driverloaded y|n]
[--lockopt String]
[--longhelp]
[--nolocking]
[--profile String]
[--version]

OPTIONS

-A|--autobackup y|n

Specifies if metadata should be backed up automatically after a change. Enabling this is strongly advised! See `vgcfgbackup(8)` for more information.

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf` settings. The String arg uses the same format as `lvm.conf`, or may use section/field syntax. See `lvm.conf(5)` for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

-h|--help

Display help text.

--lockopt String

Used to pass options for special cases to `lvmlockd`. See `lvmlockd(8)` for more information.

--longhelp

Display long help text.

--nolocking

Disable locking.

--noudevsync

Disables udev synchronisation. The process will not wait for notification from udev. It will continue irrespective of any possible udev processing in the background. Only use this if udev is not running or has rules that ignore the devices LVM creates.

--profile String

An alias for --commandprofile or --metadataprofile, depending on the command.

-q|--quiet ...

Suppress output and log messages. Overrides --debug and --verbose. Repeat once to also suppress any prompts with answer 'no'.

--reportformat basic|json

Overrides current output format for reports which is defined globally by the report/output_format setting in lvm.conf. basic is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. json produces report output in JSON format. See lvmreport(7) for more information.

-t|--test

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

-v|--verbose ...

Set verbose level. Repeat from 1 to 4 times to increase the detail of messages sent to stdout and stderr.

--version

Display version information.

-y|--yes

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see -qq.)

VARIABLES

VG

Volume Group name. See `lvm(8)` for valid names.

LV

Logical Volume name. See `lvm(8)` for valid names. An LV positional argument usually includes the VG name and LV name, e.g. VG/LV.

String

See the option description for information about the string content.

Size[UNIT]

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: bBsSkKmMgGtTpPeE. b|B is bytes, s|S is sectors of 512 bytes, k|K is kilobytes, m|M is megabytes, g|G is gigabytes, t|T is terabytes, p|P is petabytes, e|E is exabytes. (This should not be confused with the output control --units, where capital letters mean multiple of 1000.)

ENVIRONMENT VARIABLES

See `lvm(8)` for information about environment variables used by `lvm`. For example, `LVM_VG_NAME` can generally be substituted for a required VG parameter.

EXAMPLES

Rename "lvold" to "lvnew":

```
lvrename /dev/vg02/lvold vg02/lvnew
```

An alternate syntax to rename "lvold" to "lvnew":

```
lvrename vg02 lvold lvnew
```

SEE ALSO

`lvm(8)` `lvm.conf(5)` `lvmconfig(8)`

`pvchange(8)` `pvck(8)` `pvcreate(8)` `pvdisplay(8)` `pvmove(8)` `pvremove(8)` `pvresize(8)`

`pvs(8)` `pvscan(8)`

`vgcfgbackup(8)` `vgcfgrestore(8)` `vgchange(8)` `vgck(8)` `vgcreate(8)` `vgconvert(8)` `vgdisplay(8)`

`vgexport(8)` `vgextend(8)` `vgimport(8)` `vgimportclone(8)` `vgmerge(8)` `vgmknfs(8)`

odes(8) vgreduce(8) vgremove(8) vgrename(8) vgs(8) vgscan(8) vgsplit(8)

lvcreate(8) lvchange(8) lvconvert(8) lvdisplay(8) lvextend(8) lvreduce(8) lvre?

move(8) lvrename(8) lvresize(8) lvs(8) lvscan(8)

lvm-fullreport(8) lvm-lvpoll(8) lvm2-activation-generator(8) blkdeactivate(8) lvm?

dump(8)

dmeventd(8) lvmpolld(8) lvmlockd(8) lvmlockctl(8) cmirror(8) lvmdbusd(8)

lvmsystemid(7) lvmreport(7) lvmraid(7) lvmthin(7) lvmcache(7)

Red Hat, Inc.

LVM TOOLS 2.03.07(2) (2019-11-30)

LVRENAME(8)