



Rocky Enterprise Linux 9.2 Manual Pages on command 'vgdisplay.8'

C:\>man vgdisplay.8

VGDISPLAY(8) System Manager's Manual VGDISPLAY(8)

NAME

vgdisplay - Display volume group information

SYNOPSIS

vgdisplay

[option_args]

[position_args]

DESCRIPTION

vgdisplay shows the attributes of VGs, and the associated PVs and LVs.

vgfs(8) is a preferred alternative that shows the same information and more, using a more compact and configurable output format.

USAGE

vgdisplay

[-A|--activevolumegroups]

[-c|--colon]

[-C|--columns]

[-o|--options String]

[-S|--select String]

[-s|--short]

[-O|--sort String]

[--aligned]

[--binary]

[--configreport log|vg|lv|pv|pvseg|seg]
[--foreign]
[--ignorelockingfailure]
[--logonly]
[--noheadings]
[--nosuffix]
[--readonly]
[--reportformat basic|json]
[--shared]
[--separator String]
[--unbuffered]
[--units r|R|h|H|b|B|s|S|k|K|m|M|g|G|t|T|p|P|e|E]
[COMMON_OPTIONS]
[VG|Tag ...]

Common options for lvm:

[-d|--debug]
[-h|--help]
[-q|--quiet]
[-t|--test]
[-v|--verbose]
[-y|--yes]
[--commandprofile String]
[--config String]
[--driverloaded y|n]
[--lockopt String]
[--longhelp]
[--nolocking]
[--profile String]
[--version]

OPTIONS

-A|--activevolumegroups

Only select active VGs. The VG is considered active if at least one of its
LVs is active.

--aligned

Use with --separator to align the output columns

--binary

Use binary values "0" or "1" instead of descriptive literal values for columns that have exactly two valid values to report (not counting the "unknown" value which denotes that the value could not be determined).

-c|--colon

Generate colon separated output for easier parsing in scripts or programs. Also see vgs(8) which provides considerably more control over the output.

-C|--columns

Display output in columns, the equivalent of vgs(8). Options listed are the same as options given in vgs(8).

--commandprofile String

The command profile to use for command configuration. See lvm.conf(5) for more information about profiles.

--config String

Config settings for the command. These override lvm.conf settings. The String arg uses the same format as lvm.conf, or may use section/field syntax. See lvm.conf(5) for more information about config.

--configreport log|vg|lv|pv|pvseg|seg

See lvmreport(7).

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

--foreign

Report/display foreign VGs that would otherwise be skipped. See lvmsystemid(7) for more information about foreign VGs.

-h|--help

Display help text.

--ignorelockingfailure

Allows a command to continue with read-only metadata operations after lock?

ing failures.

`--lockopt` String

Used to pass options for special cases to `lvmlockd`. See `lvmlockd(8)` for more information.

`--logonly`

Suppress command report and display only log report.

`--longhelp`

Display long help text.

`--noheadings`

Suppress the headings line that is normally the first line of output. Useful if grepping the output.

`--nolocking`

Disable locking.

`--nosuffix`

Suppress the suffix on output sizes. Use with `--units` (except `h` and `H`) if processing the output.

`-o|--options` String

Comma-separated, ordered list of fields to display in columns. String argument syntax is: `[+|-|#]Field1[,Field2 ...]` The prefix `+` will append the specified fields to the default fields, `-` will remove the specified fields from the default fields, and `#` will compact specified fields (removing them when empty for all rows.) Use `-o help` to view the list of all available fields. Use separate lists of fields to add, remove or compact by repeating the `-o` option: `-o+field1,field2 -o-field3,field4 -o#field5`. These lists are evaluated from left to right. Use field name `lv_all` to view all LV fields, `vg_all` all VG fields, `pv_all` all PV fields, `pvseg_all` all PV segment fields, `seg_all` all LV segment fields, and `pvseg_all` all PV segment columns. See the `lvm.conf` report section for more config options. See `lvmreport(7)` for more information about reporting.

`--profile` String

An alias for `--commandprofile` or `--metadataprofile`, depending on the command.

`-q|--quiet ...`

Suppress output and log messages. Overrides `--debug` and `--verbose`. Repeat once to also suppress any prompts with answer 'no'.

`--readonly`

Run the command in a special read-only mode which will read on-disk metadata without needing to take any locks. This can be used to peek inside metadata used by a virtual machine image while the virtual machine is running. No attempt will be made to communicate with the device-mapper kernel driver, so this option is unable to report whether or not LVs are actually in use.

`--reportformat basic|json`

Overrides current output format for reports which is defined globally by the `report/output_format` setting in `lvm.conf`. `basic` is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. `json` produces report output in JSON format. See `lvmreport(7)` for more information.

`-S|--select String`

Select objects for processing and reporting based on specified criteria.

The criteria syntax is described by `--select help` and `lvmreport(7)`. For reporting commands, one row is displayed for each object matching the criteria. See `--options help` for selectable object fields. Rows can be displayed with an additional "selected" field (`-o selected`) showing 1 if the row matches the selection and 0 otherwise. For non-reporting commands which process LVM entities, the selection is used to choose items to process.

`--separator String`

String to use to separate each column. Useful if grepping the output.

`--shared`

Report/display shared VGs that would otherwise be skipped when `lvmlockd` is not being used on the host. See `lvmlockd(8)` for more information about shared VGs.

`-s|--short`

Give a short listing showing the existence of VGs.

`-O|--sort String`

Comma-separated ordered list of columns to sort by. Replaces the default se?

lection. Precede any column with - for a reverse sort on that column.

-t|--test

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

--unbuffered

Produce output immediately without sorting or aligning the columns properly.

--units r|R|h|H|b|B|s|S|k|K|m|M|g|G|t|T|p|P|e|E

All sizes are output in these units: human-(r)eadable with '<' rounding indicator, (h)uman-readable, (b)ytes, (s)ectors, (k)ilobytes, (m)egabytes, (g)igabytes, (t)erabytes, (p)etabytes, (e)xabytes. Capitalise to use multiples of 1000 (S.I.) instead of 1024. Custom units can be specified, e.g. --units 3M.

-v|--verbose ...

Set verbose level. Repeat from 1 to 4 times to increase the detail of messages sent to stdout and stderr.

--version

Display version information.

-y|--yes

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see -qq.)

VARIABLES

VG

Volume Group name. See lvm(8) for valid names.

Tag

Tag name. See lvm(8) for information about tag names and using tags in place of a VG, LV or PV.

String

See the option description for information about the string content.

Size[UNIT]

Size is an input number that accepts an optional unit. Input units are al?

ways treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors of 512 bytes, k|K is kilobytes, m|M is megabytes, g|G is gigabytes, t|T is terabytes, p|P is petabytes, e|E is exabytes. (This should not be confused with the output control --units, where capital letters mean multiple of 1000.)

ENVIRONMENT VARIABLES

See [lvm\(8\)](#) for information about environment variables used by lvm. For example, LVM_VG_NAME can generally be substituted for a required VG parameter.

SEE ALSO

[lvm\(8\)](#) [lvm.conf\(5\)](#) [lvmconfig\(8\)](#)
[pvchange\(8\)](#) [pvck\(8\)](#) [pvcreate\(8\)](#) [pvdisplay\(8\)](#) [pvmove\(8\)](#) [pvremove\(8\)](#) [pvresize\(8\)](#)
[pvs\(8\)](#) [pvscan\(8\)](#)
[vgcfgbackup\(8\)](#) [vgcfgrestore\(8\)](#) [vgchange\(8\)](#) [vgck\(8\)](#) [vgcreate\(8\)](#) [vgconvert\(8\)](#) [vgdisplay\(8\)](#) [vgexport\(8\)](#) [vgextend\(8\)](#) [vgimport\(8\)](#) [vgimportclone\(8\)](#) [vgmerge\(8\)](#) [vgmknodes\(8\)](#) [vgreduce\(8\)](#) [vgremove\(8\)](#) [vgrename\(8\)](#) [vgs\(8\)](#) [vgscan\(8\)](#) [vgsplit\(8\)](#)
[lvcreate\(8\)](#) [lvchange\(8\)](#) [lvconvert\(8\)](#) [lvdisplay\(8\)](#) [lvextend\(8\)](#) [lvreduce\(8\)](#) [lvremove\(8\)](#) [lvrename\(8\)](#) [lvresize\(8\)](#) [lvs\(8\)](#) [lvscan\(8\)](#)
[lvm-fullreport\(8\)](#) [lvm-lvpoll\(8\)](#) [lvm2-activation-generator\(8\)](#) [blkdeactivate\(8\)](#) [lvm?dump\(8\)](#)
[dmeventd\(8\)](#) [lvmpolld\(8\)](#) [lvmlockd\(8\)](#) [lvmlockctl\(8\)](#) [cmirrorrd\(8\)](#) [lvmdbusd\(8\)](#)
[lvmsystemid\(7\)](#) [lvmreport\(7\)](#) [lvraid\(7\)](#) [lvthin\(7\)](#) [lvmdcache\(7\)](#)

Red Hat, Inc.

LVM TOOLS 2.03.07(2) (2019-11-30)

VGDISPLAY(8)