



Rocky Enterprise Linux 9.2 Manual Pages on command 'vgremove.8'

C:~>man vgrremove.8

VGREMOVE(8) System Manager's Manual VGREMOVE(8)

NAME

vgremove - Remove volume group(s)

SYNOPSIS

vgremove position_args
[option_args]

DESCRIPTION

vgremove removes one or more VGs. If LVs exist in the VG, a prompt is used to confirm LV removal.

If one or more PVs in the VG are lost, consider `vgreduce --removemissing` to make the VG metadata consistent again.

Repeat the `force` option (`-ff`) to forcibly remove LVs in the VG without confirmation.

USAGE

vgremove VG|Tag|Select ...
[`-f|--force`]
[`-S|--select String`]
[`--noudevsync`]
[`--reportformat basic|json`]
[COMMON_OPTIONS]

Common options for lvm:

[`-d|--debug`]

[-h|--help]
[-q|--quiet]
[-t|--test]
[-v|--verbose]
[-y|--yes]
[--commandprofile String]
[--config String]
[--driverloaded y|n]
[--lockopt String]
[--longhelp]
[--nolocking]
[--profile String]
[--version]

OPTIONS

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf` settings. The String arg uses the same format as `lvm.conf`, or may use section/field syntax. See `lvm.conf(5)` for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

-f|--force ...

Override various checks, confirmations and protections. Use with extreme caution.

-h|--help

Display help text.

--lockopt String

Used to pass options for special cases to lvmlockd. See lvmlockd(8) for more information.

`--longhelp`

Display long help text.

`--nolocking`

Disable locking.

`--noudevsync`

Disables udev synchronisation. The process will not wait for notification from udev. It will continue irrespective of any possible udev processing in the background. Only use this if udev is not running or has rules that ignore the devices LVM creates.

`--profile String`

An alias for `--commandprofile` or `--metadataprofile`, depending on the command.

`-q|--quiet ...`

Suppress output and log messages. Overrides `--debug` and `--verbose`. Repeat once to also suppress any prompts with answer 'no'.

`--reportformat basic|json`

Overrides current output format for reports which is defined globally by the `report/output_format` setting in `lvm.conf`. `basic` is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. `json` produces report output in JSON format. See `lvmreport(7)` for more information.

`-S|--select String`

Select objects for processing and reporting based on specified criteria.

The criteria syntax is described by `--select help` and `lvmreport(7)`. For reporting commands, one row is displayed for each object matching the criteria. See `--options help` for selectable object fields. Rows can be displayed with an additional "selected" field (`-o selected`) showing 1 if the row matches the selection and 0 otherwise. For non-reporting commands which process LVM entities, the selection is used to choose items to process.

`-t|--test`

Run in test mode. Commands will not update metadata. This is implemented by

disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

`-v|--verbose ...`

Set verbose level. Repeat from 1 to 4 times to increase the detail of messages sent to stdout and stderr.

`--version`

Display version information.

`-y|--yes`

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see `-qq`.)

VARIABLES

VG

Volume Group name. See `lvm(8)` for valid names.

Tag

Tag name. See `lvm(8)` for information about tag names and using tags in place of a VG, LV or PV.

Select

`Select` indicates that a required positional parameter can be omitted if the `--select` option is used. No arg appears in this position.

String

See the option description for information about the string content.

Size[UNIT]

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors of 512 bytes, k|K is kilobytes, m|M is megabytes, g|G is gigabytes, t|T is terabytes, p|P is petabytes, e|E is exabytes. (This should not be confused with the output control `--units`, where capital letters mean multiple of 1000.)

ENVIRONMENT VARIABLES

See `lvm(8)` for information about environment variables used by `lvm`. For example, `LVM_VG_NAME` can generally be substituted for a required VG parameter.

SEE ALSO

`lvm(8)` `lvm.conf(5)` `lvmconfig(8)`

`pvchange(8)` `pvck(8)` `pvcreate(8)` `pvdisk(8)` `pvmove(8)` `pvremove(8)` `pvresize(8)`

`pvs(8)` `pvscan(8)`

`vgcfgbackup(8)` `vgcfgrestore(8)` `vgchange(8)` `vgck(8)` `vgcreate(8)` `vgconvert(8)` `vgdis?`

`play(8)` `vgexport(8)` `vgextend(8)` `vgimport(8)` `vgimportclone(8)` `vgmerge(8)` `vgmkn?`

`odes(8)` `vgreduce(8)` `vgremove(8)` `vgrename(8)` `vgs(8)` `vgscan(8)` `vgsplit(8)`

`lvcreate(8)` `lvchange(8)` `lvconvert(8)` `lvdisplay(8)` `lvextend(8)` `lvreduce(8)` `lvre?`

`move(8)` `lvrename(8)` `lvresize(8)` `lvs(8)` `lvscan(8)`

`lvm-fullreport(8)` `lvm-lvpoll(8)` `lvm2-activation-generator(8)` `blkdeactivate(8)` `lvm?`

`dump(8)`

`dmeventd(8)` `lvmpolld(8)` `lvmlockd(8)` `lvmlockctl(8)` `cmirror(8)` `lvdbusd(8)`

`lvmsystemid(7)` `lvmreport(7)` `lvraid(7)` `lvthin(7)` `lvmdcache(7)`

Red Hat, Inc.

LVM TOOLS 2.03.07(2) (2019-11-30)

VGREMOVE(8)