



*Full credit is given to the above companies including the OS that this PDF file was generated!*

## **Red Hat Enterprise Linux Release 9.2 Manual Pages on 'X509\_STORE\_CTX\_get0\_chain.3ossl' command**

```
$ man X509_STORE_CTX_get0_chain.3ossl
```

```
X509_STORE_CTX_NEW(3ossl)      OpenSSL      X509_STORE_CTX_NEW(3ossl)
```

### NAME

X509\_STORE\_CTX\_new\_ex, X509\_STORE\_CTX\_new, X509\_STORE\_CTX\_cleanup,  
X509\_STORE\_CTX\_free, X509\_STORE\_CTX\_init,  
X509\_STORE\_CTX\_set0\_trusted\_stack, X509\_STORE\_CTX\_set\_cert,  
X509\_STORE\_CTX\_set0\_crls, X509\_STORE\_CTX\_get0\_param,  
X509\_STORE\_CTX\_set0\_param, X509\_STORE\_CTX\_get0\_untrusted,  
X509\_STORE\_CTX\_set0\_untrusted, X509\_STORE\_CTX\_get\_num\_untrusted,  
X509\_STORE\_CTX\_get0\_chain, X509\_STORE\_CTX\_set0\_verified\_chain,  
X509\_STORE\_CTX\_set\_default, X509\_STORE\_CTX\_set\_verify,  
X509\_STORE\_CTX\_verify\_fn, X509\_STORE\_CTX\_set\_purpose,  
X509\_STORE\_CTX\_set\_trust, X509\_STORE\_CTX\_purpose\_inherit -  
X509\_STORE\_CTX initialisation

### SYNOPSIS

```
#include <openssl/x509_vfy.h>
```

```
X509_STORE_CTX *X509_STORE_CTX_new_ex(OSSL_LIB_CTX *libctx, const char *propq);
```

```
X509_STORE_CTX *X509_STORE_CTX_new(void);
```

```
void X509_STORE_CTX_cleanup(X509_STORE_CTX *ctx);
```

```
void X509_STORE_CTX_free(X509_STORE_CTX *ctx);
```

```

int X509_STORE_CTX_init(X509_STORE_CTX *ctx, X509_STORE *trust_store,
                       X509 *target, STACK_OF(X509) *untrusted);

void X509_STORE_CTX_set0_trusted_stack(X509_STORE_CTX *ctx, STACK_OF(X509) *sk);

void X509_STORE_CTX_set_cert(X509_STORE_CTX *ctx, X509 *target);
void X509_STORE_CTX_set0_crls(X509_STORE_CTX *ctx, STACK_OF(X509_CRL) *sk);

X509_VERIFY_PARAM *X509_STORE_CTX_get0_param(const X509_STORE_CTX *ctx);
void X509_STORE_CTX_set0_param(X509_STORE_CTX *ctx, X509_VERIFY_PARAM *param);

STACK_OF(X509)* X509_STORE_CTX_get0_untrusted(const X509_STORE_CTX *ctx);
void X509_STORE_CTX_set0_untrusted(X509_STORE_CTX *ctx, STACK_OF(X509) *sk);

int X509_STORE_CTX_get_num_untrusted(const X509_STORE_CTX *ctx);
STACK_OF(X509) *X509_STORE_CTX_get0_chain(const X509_STORE_CTX *ctx);
void X509_STORE_CTX_set0_verified_chain(X509_STORE_CTX *ctx, STACK_OF(X509) *chain);

int X509_STORE_CTX_set_default(X509_STORE_CTX *ctx, const char *name);
typedef int (*X509_STORE_CTX_verify_fn)(X509_STORE_CTX *);
void X509_STORE_CTX_set_verify(X509_STORE_CTX *ctx, X509_STORE_CTX_verify_fn verify);

int X509_STORE_CTX_set_purpose(X509_STORE_CTX *ctx, int purpose);
int X509_STORE_CTX_set_trust(X509_STORE_CTX *ctx, int trust);
int X509_STORE_CTX_purpose_inherit(X509_STORE_CTX *ctx, int def_purpose,
                                  int purpose, int trust);

```

## DESCRIPTION

These functions initialise an X509\_STORE\_CTX structure for subsequent use by X509\_verify\_cert(3) or X509\_STORE\_CTX\_verify(3).

X509\_STORE\_CTX\_new\_ex() returns a newly initialised X509\_STORE\_CTX structure associated with the specified library context libctx and

property query string propq. Any cryptographic algorithms fetched while performing processing with the X509\_STORE\_CTX will use that library context and property query string.

X509\_STORE\_CTX\_new() is the same as X509\_STORE\_CTX\_new\_ex() except that the default library context and a NULL property query string are used.

X509\_STORE\_CTX\_cleanup() internally cleans up an X509\_STORE\_CTX structure. It is used by X509\_STORE\_CTX\_init() and X509\_STORE\_CTX\_free().

X509\_STORE\_CTX\_free() completely frees up ctx. After this call ctx is no longer valid. If ctx is NULL nothing is done.

It must be called before each call to X509\_verify\_cert(3) or X509\_STORE\_CTX\_verify(3), i.e., a context is only good for one verification. If you want to verify a further certificate or chain with the same ctx then you must call X509\_STORE\_CTX\_init() again. The trusted certificate store is set to trust\_store of type X509\_STORE.

This may be NULL because there are no trusted certificates or because they are provided simply as a list using

X509\_STORE\_CTX\_set0\_trusted\_stack(). The certificate to be verified is set to target, and a list of additional certificates may be provided in untrusted, which will be untrusted but may be used to build the chain.

Each of the trust\_store, target and untrusted parameters can be NULL.

Yet note that X509\_verify\_cert(3) and X509\_STORE\_CTX\_verify(3) will need a verification target. This can also be set using

X509\_STORE\_CTX\_set\_cert(). For X509\_STORE\_CTX\_verify(3), which takes by default the first element of the list of untrusted certificates as its verification target, this can be also set indirectly using

X509\_STORE\_CTX\_set0\_untrusted().

X509\_STORE\_CTX\_set0\_trusted\_stack() sets the set of trusted

certificates of ctx to sk. This is an alternative way of specifying trusted certificates instead of using an X509\_STORE where its complexity is not needed or to make sure that only the given set sk of certificates are trusted.

X509\_STORE\_CTX\_set\_cert() sets the target certificate to be verified in ctx to target.

X509\_STORE\_CTX\_set0\_verified\_chain() sets the validated chain to chain. Ownership of the chain is transferred to ctx, and so it should not be free'd by the caller.

X509\_STORE\_CTX\_get0\_chain() returns the internal pointer used by the ctx that contains the constructed (output) chain.

X509\_STORE\_CTX\_set0\_crls() sets a set of CRLs to use to aid certificate verification to sk. These CRLs will only be used if CRL verification is enabled in the associated X509\_VERIFY\_PARAM structure. This might be used where additional "useful" CRLs are supplied as part of a protocol, for example in a PKCS#7 structure.

X509\_STORE\_CTX\_get0\_param() retrieves an internal pointer to the verification parameters associated with ctx.

X509\_STORE\_CTX\_set0\_param() sets the internal verification parameter pointer to param. After this call param should not be used.

X509\_STORE\_CTX\_get0\_untrusted() retrieves an internal pointer to the stack of untrusted certificates associated with ctx.

X509\_STORE\_CTX\_set0\_untrusted() sets the internal pointer to the stack of untrusted certificates associated with ctx to sk.

X509\_STORE\_CTX\_verify() will take the first element, if any, as its

default target if the target certificate is not set explicitly.

X509\_STORE\_CTX\_get\_num\_untrusted() returns the number of untrusted certificates that were used in building the chain. This is can be used after calling X509\_verify\_cert(3) and similar functions. With X509\_STORE\_CTX\_verify(3), this does not count the first chain element.

X509\_STORE\_CTX\_get0\_chain() returns the internal pointer used by the ctx that contains the validated chain.

Details of the chain building and checking process are described in "Certification Path Building" in openssl-verification-options(1) and "Certification Path Validation" in openssl-verification-options(1).

X509\_STORE\_CTX\_set0\_verified\_chain() sets the validated chain used by ctx to be chain. Ownership of the chain is transferred to ctx, and so it should not be free'd by the caller.

X509\_STORE\_CTX\_set\_default() looks up and sets the default verification method to name. This uses the function X509\_VERIFY\_PARAM\_lookup() to find an appropriate set of parameters from the purpose identifier name. Currently defined purposes are "sslclient", "sslserver", "nssslserver", "smimesign", "smimeencrypt", "crlsign", "ocsp-helper", "timestampsign", and "any".

X509\_STORE\_CTX\_set\_verify() provides the capability for overriding the default verify function. This function is responsible for verifying chain signatures and expiration times.

A verify function is defined as an X509\_STORE\_CTX\_verify type which has the following signature:

```
int (*verify)(X509_STORE_CTX *);
```

This function should receive the current X509\_STORE\_CTX as a parameter and return 1 on success or 0 on failure.

X509 certificates may contain information about what purposes keys contained within them can be used for. For example "TLS WWW Server Authentication" or "Email Protection". This "key usage" information is held internally to the certificate itself. In addition the trust store containing trusted certificates can declare what purposes we trust different certificates for. This "trust" information is not held within the certificate itself but is "meta" information held alongside it. This "meta" information is associated with the certificate after it is issued and could be determined by a system administrator. For example a certificate might declare that it is suitable for use for both "TLS WWW Server Authentication" and "TLS Client Authentication", but a system administrator might only trust it for the former. An X.509 certificate extension exists that can record extended key usage information to supplement the purpose information described above. This extended mechanism is arbitrarily extensible and not well suited for a generic library API; applications that need to validate extended key usage information in certificates will need to define a custom "purpose" (see below) or supply a nondefault verification callback (X509\_STORE\_set\_verify\_cb\_func(3)).

X509\_STORE\_CTX\_set\_purpose() sets the purpose for the target certificate being verified in the ctx. Built-in available values for the purpose argument are X509\_PURPOSE\_SSL\_CLIENT, X509\_PURPOSE\_SSL\_SERVER, X509\_PURPOSE\_NS\_SSL\_SERVER, X509\_PURPOSE\_SMIME\_SIGN, X509\_PURPOSE\_SMIME\_ENCRYPT, X509\_PURPOSE\_CRL\_SIGN, X509\_PURPOSE\_ANY, X509\_PURPOSE\_OCSP\_HELPER and X509\_PURPOSE\_TIMESTAMP\_SIGN. It is also possible to create a custom purpose value. Setting a purpose will ensure that the key usage declared within certificates in the chain being verified is consistent

with that purpose as well as, potentially, other checks. Every purpose also has an associated default trust value which will also be set at the same time. During verification this trust setting will be verified to check it is consistent with the trust set by the system administrator for certificates in the chain.

X509\_STORE\_CTX\_set\_trust() sets the trust value for the target certificate being verified in the ctx. Built-in available values for the trust argument are X509\_TRUST\_COMPAT, X509\_TRUST\_SSL\_CLIENT, X509\_TRUST\_SSL\_SERVER, X509\_TRUST\_EMAIL, X509\_TRUST\_OBJECT\_SIGN, X509\_TRUST\_OCSP\_SIGN, X509\_TRUST\_OCSP\_REQUEST and X509\_TRUST\_TSA. It is also possible to create a custom trust value. Since X509\_STORE\_CTX\_set\_purpose() also sets the trust value it is normally sufficient to only call that function. If both are called then X509\_STORE\_CTX\_set\_trust() should be called after X509\_STORE\_CTX\_set\_purpose() since the trust setting of the last call will be used.

It should not normally be necessary for end user applications to call X509\_STORE\_CTX\_purpose\_inherit() directly. Typically applications should call X509\_STORE\_CTX\_set\_purpose() or X509\_STORE\_CTX\_set\_trust() instead. Using this function it is possible to set the purpose and trust values for the ctx at the same time. Both ctx and its internal verification parameter pointer must not be NULL. The def\_purpose and purpose arguments can have the same purpose values as described for X509\_STORE\_CTX\_set\_purpose() above. The trust argument can have the same trust values as described in X509\_STORE\_CTX\_set\_trust() above. Any of the def\_purpose, purpose or trust values may also have the value 0 to indicate that the supplied parameter should be ignored. After calling this function the purpose to be used for verification is set from the purpose argument unless the purpose was already set in ctx before, and the trust is set from the trust argument unless the trust was already set in ctx before. If trust is 0 then the trust value will

be set from the default trust value for purpose. If the default trust value for the purpose is X509\_TRUST\_DEFAULT and trust is 0 then the default trust value associated with the def\_purpose value is used for the trust setting instead.

## NOTES

The certificates and CRLs in a store are used internally and should not be freed up until after the associated X509\_STORE\_CTX is freed.

## BUGS

The certificates and CRLs in a context are used internally and should not be freed up until after the associated X509\_STORE\_CTX is freed.

Copies should be made or reference counts increased instead.

## RETURN VALUES

X509\_STORE\_CTX\_new() returns a newly allocated context or NULL if an error occurred.

X509\_STORE\_CTX\_init() returns 1 for success or 0 if an error occurred.

X509\_STORE\_CTX\_get0\_param() returns a pointer to an X509\_VERIFY\_PARAM structure or NULL if an error occurred.

X509\_STORE\_CTX\_cleanup(), X509\_STORE\_CTX\_free(), X509\_STORE\_CTX\_set0\_trusted\_stack(), X509\_STORE\_CTX\_set\_cert(), X509\_STORE\_CTX\_set0\_crls() and X509\_STORE\_CTX\_set0\_param() do not return values.

X509\_STORE\_CTX\_set\_default() returns 1 for success or 0 if an error occurred.

X509\_STORE\_CTX\_get\_num\_untrusted() returns the number of untrusted certificates used.

## SEE ALSO

X509\_verify\_cert(3), X509\_STORE\_CTX\_verify(3),  
X509\_VERIFY\_PARAM\_set\_flags(3)

## HISTORY

The X509\_STORE\_CTX\_set0\_crls() function was added in OpenSSL 1.0.0.

The X509\_STORE\_CTX\_get\_num\_untrusted() function was added in OpenSSL 1.1.0. The X509\_STORE\_CTX\_new\_ex() function was added in OpenSSL 3.0.

There is no need to call X509\_STORE\_CTX\_cleanup() explicitly since OpenSSL 3.0.

## COPYRIGHT

Copyright 2009-2022 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7                    2023-07-13        X509\_STORE\_CTX\_NEW(3openssl)