



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'dbus-send.1' command

\$ man dbus-send.1

DBUS-SEND(1) User Commands DBUS-SEND(1)

NAME

dbus-send - Send a message to a message bus

SYNOPSIS

```
dbus-send [--system | --session | --bus=ADDRESS | --peer=ADDRESS]
```

--dest=NAME [**--print-reply** [=literal]]

--reply-timeout=MSEC **--type=TYPE** OBJECT_PATH

INTERFACE MEMBER [CONTENTS...]

DESCRIPTION

The `dbus-send` command is used to send a message to a D-Bus message bus.

See <http://www.freedesktop.org/software/dbus/> for more information

about the big picture.

There are two well-known message buses: the systemwide message bus

(installed on many systems as the "messagebus" service) and the

per-user-login-session message bus (started each time a user logs in).

The `--system` and `--session` options direct `dbus-send` to send messages to

the system or session buses respectively. If neither is specified,

dbus-send sends to the session bus.

Nearly all uses of `dbus-send` must provide the `--dest` argument which is

the name of a connection on the bus to send the message to. If --dest

is omitted, no destination is set.

The object path and the name of the message to send must always be

specified. Following arguments, if any, are the message contents

(message arguments). These are given as type-specified values and may include containers (arrays, dicts, and variants) as described below.

```
<contents> ::= <item> | <container> [ <item> | <container>...]

<item> ::= <type>:<value>

<container> ::= <array> | <dict> | <variant>

<array> ::= array:<type>:<value>[,<value>...]

<dict> ::= dict:<type>:<type>:<key>,<value>[,<key>,<value>...]

<variant> ::= variant:<type>:<value>

<type> ::= string | int16 | uint16 | int32 | uint32 | int64 | uint64 | double | byte | boolean | objpath
```

D-Bus supports more types than these, but dbus-send currently does not.

Also, dbus-send does not permit empty containers or nested containers (e.g. arrays of variants).

Here is an example invocation:

```
dbus-send --dest=org.freedesktop.ExampleName \
          /org/freedesktop/sample/object/name \
          org.freedesktop.ExampleInterface.ExampleMethod \
          int32:47 string:'hello world' double:65.32 \
          array:string:"1st item","next item","last item" \
          dict:string:int32:"one",1,"two",2,"three",3 \
          variant:int32:-8 \
          objpath:/org/freedesktop/sample/object/name
```

Note that the interface is separated from a method or signal name by a dot, though in the actual protocol the interface and the interface member are separate fields.

OPTIONS

The following options are supported:

--dest=NAME

Specify the name of the connection to receive the message.

--print-reply

Block for a reply to the message sent, and print any reply received in a human-readable form. It also means the message type (**--type=**) is `method_call`.

--print-reply=literal

Block for a reply to the message sent, and print the body of the reply. If the reply is an object path or a string, it is printed literally, with no punctuation, escape characters etc.

--reply-timeout=MSEC

Wait for a reply for up to MSEC milliseconds. The default is implementation?defined, typically 25 seconds.

--system

Send to the system message bus.

--session

Send to the session message bus. (This is the default.)

--bus=ADDRESS

Register on a message bus at ADDRESS, typically a dbus-daemon.

--peer=ADDRESS

Send to a non-message-bus D-Bus server at ADDRESS. In this case dbus-send will not call the Hello method.

--type=TYPE

Specify method_call or signal (defaults to "signal").

AUTHOR

dbus-send was written by Philip Blundell.

BUGS

Please send bug reports to the D-Bus mailing list or bug tracker, see
<http://www.freedesktop.org/software/dbus/>