



*Full credit is given to the above companies including the OS that this PDF file was generated!*

***Rocky Enterprise Linux 9.2 Manual Pages on command 'OPENSSL\_VERSION\_TEXT.3ossl'***

***\$ man OPENSSL\_VERSION\_TEXT.3ossl***

OPENSSL\_VERSION(3ossl)      OpenSSL      OPENSSL\_VERSION(3ossl)

**NAME**

OPENSSL\_VERSION\_MAJOR, OPENSSL\_VERSION\_MINOR, OPENSSL\_VERSION\_PATCH,  
OPENSSL\_VERSION\_PRE\_RELEASE, OPENSSL\_VERSION\_BUILD\_METADATA,  
OPENSSL\_VERSION\_TEXT, OPENSSL\_VERSION\_PREREQ, OPENSSL\_version\_major,  
OPENSSL\_version\_minor, OPENSSL\_version\_patch,  
OPENSSL\_version\_pre\_release, OPENSSL\_version\_build\_metadata,  
OpenSSL\_version, OPENSSL\_VERSION\_NUMBER, OpenSSL\_version\_num,  
OPENSSL\_info - get OpenSSL version number and other information

**SYNOPSIS**

```
#include <openssl/opensslv.h>

#define OPENSSL_VERSION_MAJOR x
#define OPENSSL_VERSION_MINOR y
#define OPENSSL_VERSION_PATCH z
```

```

/* The definitions here are typical release values */
#define OPENSSSL_VERSION_PRE_RELEASE ""
#define OPENSSSL_VERSION_BUILD_METADATA ""

#define OPENSSSL_VERSION_TEXT "OpenSSL x.y.z xx XXX xxxx"

#define OPENSSSL_VERSION_PREREQ(maj,min)

#include <openssl/crypto.h>

unsigned int OPENSSSL_version_major(void);
unsigned int OPENSSSL_version_minor(void);
unsigned int OPENSSSL_version_patch(void);
const char *OPENSSSL_version_pre_release(void);
const char *OPENSSSL_version_build_metadata(void);

const char *OpenSSL_version(int t);

const char *OPENSSSL_info(int t);

/* from openssl/opensslv.h */
#define OPENSSSL_VERSION_NUMBER 0xnnnnnnnnL

/* from openssl/crypto.h */
unsigned long OpenSSL_version_num();

```

## DESCRIPTION

### Macros

The three macros `OPENSSSL_VERSION_MAJOR`, `OPENSSSL_VERSION_MINOR` and `OPENSSSL_VERSION_PATCH` represent the three parts of a version identifier, `MAJOR.MINOR.PATCH`.

The macro `OPENSSSL_VERSION_PRE_RELEASE` is an added bit of text that

indicates that this is a pre-release version, such as "-dev" for an ongoing development snapshot or "-alpha3" for an alpha release. The value must be a string.

The macro `OPENSSL_VERSION_BUILD_METADATA` is extra information, reserved for other parties, such as "+fips", or "+vendor.1"). The OpenSSL project will not touch this macro (will leave it an empty string). The value must be a string.

`OPENSSL_VERSION_STR` is a convenience macro to get the short version identifier string, "MAJOR.MINOR.PATCH".

`OPENSSL_FULL_VERSION_STR` is a convenience macro to get the longer version identifier string, which combines `OPENSSL_VERSION_STR`, `OPENSSL_VERSION_PRE_RELEASE` and `OPENSSL_VERSION_BUILD_METADATA`.

`OPENSSL_VERSION_TEXT` is a convenience macro to get a full descriptive version text, which includes `OPENSSL_FULL_VERSION_STR` and the release date.

`OPENSSL_VERSION_PREREQ` is a useful macro for checking whether the OpenSSL version for the headers in use is at least at the given pre-requisite major (maj) and minor (min) number or not. It will evaluate to true if the header version number (`OPENSSL_VERSION_MAJOR.OPENSSL_VERSION_MINOR`) is greater than or equal to maj.min.

`OPENSSL_VERSION_NUMBER` is a combination of the major, minor and patch version into a single integer `0xMNN00PP0L`, where:

`M` is the number from `OPENSSL_VERSION_MAJOR`, in hexadecimal notation

`NN` is the number from `OPENSSL_VERSION_MINOR`, in hexadecimal notation

PP is the number from OPENSSL\_VERSION\_PATCH, in hexadecimal notation

## Functions

OPENSSL\_version\_major(), OPENSSL\_version\_minor(),  
OPENSSL\_version\_patch(), OPENSSL\_version\_pre\_release(), and  
OPENSSL\_version\_build\_metadata() return the values of the macros above  
for the build of the library, respectively.

OpenSSL\_version() returns different strings depending on t:

### OPENSSL\_VERSION

The value of OPENSSL\_VERSION\_TEXT

### OPENSSL\_VERSION\_STRING

The value of OPENSSL\_VERSION\_STR

### OPENSSL\_FULL\_VERSION\_STRING

The value of OPENSSL\_FULL\_VERSION\_STR

### OPENSSL\_CFLAGS

The compiler flags set for the compilation process in the form  
"compiler: ..." if available, or "compiler: information not  
available" otherwise.

### OPENSSL\_BUILT\_ON

The date of the build process in the form "built on: ..." if  
available or "built on: date not available" otherwise. The date  
would not be available in a reproducible build, for example.

### OPENSSL\_PLATFORM

The "Configure" target of the library build in the form "platform:  
..." if available, or "platform: information not available"

otherwise.

#### OPENSSL\_DIR

The OPENSSLDIR setting of the library build in the form

"OPENSSLDIR: "..."" if available, or "OPENSSLDIR: N/A" otherwise.

#### OPENSSL\_ENGINES\_DIR

The ENGINESDIR setting of the library build in the form

"ENGINESDIR: "..."" if available, or "ENGINESDIR: N/A" otherwise.

This option is deprecated in OpenSSL 3.0.

#### OPENSSL\_MODULES\_DIR

The MODULESDIR setting of the library build in the form

"MODULESDIR: "..."" if available, or "MODULESDIR: N/A" otherwise.

#### OPENSSL\_CPU\_INFO

The current OpenSSL cpu settings. This is the current setting of the cpu capability flags. It is usually automatically configured but may be set via an environment variable. The value has the same syntax as the environment variable. For x86 the string looks like "CPUINFO: OPENSSL\_ia32cap=0x123:0x456" or "CPUINFO: N/A" if not available.

For an unknown t, the text "not available" is returned.

OPENSSL\_info() also returns different strings depending on t:

#### OPENSSL\_INFO\_CONFIG\_DIR

The configured "OPENSSLDIR", which is the default location for OpenSSL configuration files.

#### OPENSSL\_INFO\_ENGINES\_DIR

The configured "ENGINESDIR", which is the default location for

OpenSSL engines.

#### OPENSSL\_INFO\_MODULES\_DIR

The configured "MODULESDIR", which is the default location for dynamically loadable OpenSSL modules other than engines.

#### OPENSSL\_INFO\_DSO\_EXTENSION

The configured dynamically loadable module extension.

#### OPENSSL\_INFO\_DIR\_FILENAME\_SEPARATOR

The separator between a directory specification and a filename.

Note that on some operating systems, this is not the same as the separator between directory elements.

#### OPENSSL\_INFO\_LIST\_SEPARATOR

The OpenSSL list separator. This is typically used in strings that are lists of items, such as the value of the environment variable \$PATH on Unix (where the separator is ":") or "%PATH%" on Windows (where the separator is ";").

#### OPENSSL\_INFO\_CPU\_SETTINGS

The current OpenSSL cpu settings. This is the current setting of the cpu capability flags. It is usually automatically configured but may be set via an environment variable. The value has the same syntax as the environment variable. For x86 the string looks like "OPENSSL\_ia32cap=0x123:0x456".

For an unknown t, NULL is returned.

OpenSSL\_version\_num() returns the value of OPENSSL\_VERSION\_NUMBER.

#### RETURN VALUES

OpenSSL\_version\_major(), OpenSSL\_version\_minor() and

OPENSSL\_version\_patch() return the version number parts as integers.

OPENSSL\_version\_pre\_release() and OPENSSL\_version\_build\_metadata() return the values of OPENSSL\_VERSION\_PRE\_RELEASE and OPENSSL\_VERSION\_BUILD\_METADATA respectively as constant strings. For any of them that is undefined, the empty string is returned.

OpenSSL\_version() returns constant strings.

## SEE ALSO

crypto(7)

## HISTORY

The macros and functions described here were added in OpenSSL 3.0, except for OPENSSL\_VERSION\_NUMBER and OpenSSL\_version\_num().

## COPYRIGHT

Copyright 2018-2022 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7                    2023-07-13            OPENSSL\_VERSION(3ossl)