



Rocky Enterprise Linux 9.2 Manual Pages on command 'SSL_CTX_up_ref.3ossl'

\$ man SSL_CTX_up_ref.3ossl

```
SSL_CTX_NEW(3ossl)          OpenSSL          SSL_CTX_NEW(3ossl)

NAME

    TLSv1_2_method, TLSv1_2_server_method, TLSv1_2_client_method,
    SSL_CTX_new, SSL_CTX_new_ex, SSL_CTX_up_ref, SSLv3_method,
    SSLv3_server_method, SSLv3_client_method, TLSv1_method,
    TLSv1_server_method, TLSv1_client_method, TLSv1_1_method,
    TLSv1_1_server_method, TLSv1_1_client_method, TLS_method,
    TLS_server_method, TLS_client_method, SSLv23_method,
    SSLv23_server_method, SSLv23_client_method, DTLS_method,
    DTLS_server_method, DTLS_client_method, DTLSv1_method,
    DTLSv1_server_method, DTLSv1_client_method, DTLSv1_2_method,
    DTLSv1_2_server_method, DTLSv1_2_client_method - create a new SSL_CTX
    object as framework for TLS/SSL or DTLS enabled functions
```

SYNOPSIS

```
#include <openssl/ssl.h>

SSL_CTX *SSL_CTX_new_ex(OSSL_LIB_CTX *libctx, const char *propq,
                        const SSL_METHOD *method);

SSL_CTX *SSL_CTX_new(const SSL_METHOD *method);
```

```
int SSL_CTX_up_ref(SSL_CTX *ctx);
const SSL_METHOD *TLS_method(void);
const SSL_METHOD *TLS_server_method(void);
const SSL_METHOD *TLS_client_method(void);
const SSL_METHOD *SSLv23_method(void);
const SSL_METHOD *SSLv23_server_method(void);
const SSL_METHOD *SSLv23_client_method(void);
#ifdef OPENSSSL_NO_SSL3_METHOD
const SSL_METHOD *SSLv3_method(void);
const SSL_METHOD *SSLv3_server_method(void);
const SSL_METHOD *SSLv3_client_method(void);
#endif
#ifdef OPENSSSL_NO_TLS1_METHOD
const SSL_METHOD *TLSv1_method(void);
const SSL_METHOD *TLSv1_server_method(void);
const SSL_METHOD *TLSv1_client_method(void);
#endif
#ifdef OPENSSSL_NO_TLS1_1_METHOD
const SSL_METHOD *TLSv1_1_method(void);
const SSL_METHOD *TLSv1_1_server_method(void);
const SSL_METHOD *TLSv1_1_client_method(void);
#endif
#ifdef OPENSSSL_NO_TLS1_2_METHOD
const SSL_METHOD *TLSv1_2_method(void);
const SSL_METHOD *TLSv1_2_server_method(void);
const SSL_METHOD *TLSv1_2_client_method(void);
#endif
const SSL_METHOD *DTLS_method(void);
const SSL_METHOD *DTLS_server_method(void);
const SSL_METHOD *DTLS_client_method(void);
#ifdef OPENSSSL_NO_DTLS1_METHOD
const SSL_METHOD *DTLSv1_method(void);
const SSL_METHOD *DTLSv1_server_method(void);
```

```

const SSL_METHOD *DTLSv1_client_method(void);

#endif

#ifdef OPENSSL_NO_DTLS1_2_METHOD

const SSL_METHOD *DTLSv1_2_method(void);

const SSL_METHOD *DTLSv1_2_server_method(void);

const SSL_METHOD *DTLSv1_2_client_method(void);

#endif

```

DESCRIPTION

SSL_CTX_new_ex() creates a new SSL_CTX object, which holds various configuration and data relevant to SSL/TLS or DTLS session establishment. These are later inherited by the SSL object representing an active session. The method parameter specifies whether the context will be used for the client or server side or both - for details see the "NOTES" below. The library context libctx (see OSSL_LIB_CTX(3)) is used to provide the cryptographic algorithms needed for the session. Any cryptographic algorithms that are used by any SSL objects created from this SSL_CTX will be fetched from the libctx using the property query string propq (see "ALGORITHM FETCHING" in crypto(7)). Either or both the libctx or propq parameters may be NULL.

SSL_CTX_new() does the same as SSL_CTX_new_ex() except that the default library context is used and no property query string is specified.

An SSL_CTX object is reference counted. Creating an SSL_CTX object for the first time increments the reference count. Freeing the SSL_CTX (using SSL_CTX_free) decrements it. When the reference count drops to zero, any memory or resources allocated to the SSL_CTX object are freed. SSL_CTX_up_ref() increments the reference count for an existing SSL_CTX structure.

An SSL_CTX object should not be changed after it is used to create any SSL objects or from multiple threads concurrently, since the implementation does not provide serialization of access for these cases.

NOTES

On session establishment, by default, no peer credentials verification

is done. This must be explicitly requested, typically using `SSL_CTX_set_verify(3)`. For verifying peer certificates many options can be set using various functions such as `SSL_CTX_load_verify_locations(3)` and `SSL_CTX_set1_param(3)`. The `X509_VERIFY_PARAM_set_purpose(3)` function can be used, also in conjunction with `SSL_CTX_get0_param(3)`, to set the intended purpose of the session. The default is `X509_PURPOSE_SSL_SERVER` on the client side and `X509_PURPOSE_SSL_CLIENT` on the server side.

The `SSL_CTX` object uses method as the connection method. Three method variants are available: a generic method (for either client or server use), a server-only method, and a client-only method.

The method parameter of `SSL_CTX_new_ex()` and `SSL_CTX_new()` can be one of the following:

`TLS_method()`, `TLS_server_method()`, `TLS_client_method()`

These are the general-purpose version-flexible SSL/TLS methods.

The actual protocol version used will be negotiated to the highest version mutually supported by the client and the server. The supported protocols are `SSLv3`, `TLSv1`, `TLSv1.1`, `TLSv1.2` and `TLSv1.3`.

Applications should use these methods, and avoid the version-specific methods described below, which are deprecated.

`SSLv23_method()`, `SSLv23_server_method()`, `SSLv23_client_method()`

These functions do not exist anymore, they have been renamed to `TLS_method()`, `TLS_server_method()` and `TLS_client_method()` respectively. Currently, the old function calls are renamed to the corresponding new ones by preprocessor macros, to ensure that existing code which uses the old function names still compiles.

However, using the old function names is deprecated and new code should call the new functions instead.

`TLSv1_2_method()`, `TLSv1_2_server_method()`, `TLSv1_2_client_method()`

A TLS/SSL connection established with these methods will only understand the `TLSv1.2` protocol. These methods are deprecated.

`TLSv1_1_method()`, `TLSv1_1_server_method()`, `TLSv1_1_client_method()`

A TLS/SSL connection established with these methods will only

understand the TLSv1.1 protocol. These methods are deprecated.

`TLSv1_method()`, `TLSv1_server_method()`, `TLSv1_client_method()`

A TLS/SSL connection established with these methods will only understand the TLSv1 protocol. These methods are deprecated.

`SSLv3_method()`, `SSLv3_server_method()`, `SSLv3_client_method()`

A TLS/SSL connection established with these methods will only understand the SSLv3 protocol. The SSLv3 protocol is deprecated and should not be used.

`DTLS_method()`, `DTLS_server_method()`, `DTLS_client_method()`

These are the version-flexible DTLS methods. Currently supported protocols are DTLS 1.0 and DTLS 1.2.

`DTLSv1_2_method()`, `DTLSv1_2_server_method()`, `DTLSv1_2_client_method()`

These are the version-specific methods for DTLSv1.2. These methods are deprecated.

`DTLSv1_method()`, `DTLSv1_server_method()`, `DTLSv1_client_method()`

These are the version-specific methods for DTLSv1. These methods are deprecated.

`SSL_CTX_new()` initializes the list of ciphers, the session cache setting, the callbacks, the keys and certificates and the options to their default values.

`TLS_method()`, `TLS_server_method()`, `TLS_client_method()`, `DTLS_method()`,

`DTLS_server_method()` and `DTLS_client_method()` are the version-flexible methods. All other methods only support one specific protocol version.

Use the version-flexible methods instead of the version specific methods.

If you want to limit the supported protocols for the version flexible

methods you can use `SSL_CTX_set_min_proto_version(3)`,

`SSL_set_min_proto_version(3)`, `SSL_CTX_set_max_proto_version(3)` and

`SSL_set_max_proto_version(3)` functions. Using these functions it is

possible to choose e.g. `TLS_server_method()` and be able to negotiate

with all possible clients, but to only allow newer protocols like TLS

1.0, TLS 1.1, TLS 1.2 or TLS 1.3.

The list of protocols available can also be limited using the

SSL_OP_NO_SSLv3, SSL_OP_NO_TLSv1, SSL_OP_NO_TLSv1_1, SSL_OP_NO_TLSv1_3, SSL_OP_NO_TLSv1_2 and SSL_OP_NO_TLSv1_3 options of the SSL_CTX_set_options(3) or SSL_set_options(3) functions, but this approach is not recommended. Clients should avoid creating "holes" in the set of protocols they support. When disabling a protocol, make sure that you also disable either all previous or all subsequent protocol versions. In clients, when a protocol version is disabled without disabling all previous protocol versions, the effect is to also disable all subsequent protocol versions.

The SSLv3 protocol is deprecated and should generally not be used. Applications should typically use SSL_CTX_set_min_proto_version(3) to set the minimum protocol to at least TLS1_VERSION.

RETURN VALUES

The following return values can occur:

NULL

The creation of a new SSL_CTX object failed. Check the error stack to find out the reason.

Pointer to an SSL_CTX object

The return value points to an allocated SSL_CTX object.

SSL_CTX_up_ref() returns 1 for success and 0 for failure.

SEE ALSO

SSL_CTX_set_options(3), SSL_CTX_free(3), SSL_CTX_set_verify(3), SSL_CTX_set1_param(3), SSL_CTX_get0_param(3), SSL_connect(3), SSL_accept(3), SSL_CTX_set_min_proto_version(3), ssl(7), SSL_set_connect_state(3)

HISTORY

Support for SSLv2 and the corresponding SSLv2_method(), SSLv2_server_method() and SSLv2_client_method() functions were removed in OpenSSL 1.1.0. SSLv23_method(), SSLv23_server_method() and SSLv23_client_method() were deprecated and the preferred TLS_method(), TLS_server_method() and TLS_client_method() functions were added in OpenSSL 1.1.0. All version-specific methods were deprecated in OpenSSL 1.1.0.

SSL_CTX_new_ex() was added in OpenSSL 3.0.

COPYRIGHT

Copyright 2000-2021 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use

this file except in compliance with the License. You can obtain a copy

in the file LICENSE in the source distribution or at

[<https://www.openssl.org/source/license.html>](https://www.openssl.org/source/license.html).

3.0.7

2023-07-13

SSL_CTX_NEW(3ossl)