



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'SSL_set_ssl_method.3ossl'

\$ man SSL_set_ssl_method.3ossl

SSL_CTX_SET_SSL_VERSION(3ossl) OpenSSL SSL_CTX_SET_SSL_VERSION(3ossl)

NAME

SSL_CTX_set_ssl_version, SSL_CTX_get_ssl_method, SSL_set_ssl_method,
SSL_get_ssl_method - choose a new TLS/SSL method

SYNOPSIS

```
#include <openssl/ssl.h>

int SSL_CTX_set_ssl_version(SSL_CTX *ctx, const SSL_METHOD *method);

const SSL_METHOD *SSL_CTX_get_ssl_method(const SSL_CTX *ctx);

int SSL_set_ssl_method(SSL *s, const SSL_METHOD *method);

const SSL_METHOD *SSL_get_ssl_method(const SSL *ssl);
```

DESCRIPTION

SSL_CTX_set_ssl_version() sets a new default TLS/SSL method for SSL objects newly created from this ctx. Most of the configuration attached to the SSL_CTX object is retained, with the exception of the configured TLS ciphers, which are reset to the default values. SSL objects already created from this SSL_CTX with SSL_new(3) are not affected, except when SSL_clear(3) is being called, as described below.

SSL_CTX_get_ssl_method() returns the SSL_METHOD which was used to

construct the `SSL_CTX`.

`SSL_set_ssl_method()` sets a new TLS/SSL method for a particular `ssl` object. It may be reset, when `SSL_clear()` is called.

`SSL_get_ssl_method()` returns a pointer to the TLS/SSL method set in `ssl`.

NOTES

The available method choices are described in `SSL_CTX_new(3)`.

When `SSL_clear(3)` is called and no session is connected to an `SSL` object, the method of the `SSL` object is reset to the method currently set in the corresponding `SSL_CTX` object.

`SSL_CTX_set_version()` has unusual semantics and no clear use case; it would usually be preferable to create a new `SSL_CTX` object than to try to reuse an existing one in this fashion. Its usage is considered deprecated.

RETURN VALUES

The following return values can occur for `SSL_CTX_set_ssl_version()` and `SSL_set_ssl_method()`:

0 The new choice failed, check the error stack to find out the reason.

1 The operation succeeded.

`SSL_CTX_get_ssl_method()` and `SSL_get_ssl_method()` always return non-NULL pointers.

SEE ALSO

`SSL_CTX_new(3)`, `SSL_new(3)`, `SSL_clear(3)`, `ssl(7)`,
`SSL_set_connect_state(3)`

HISTORY

`SSL_CTX_set_ssl_version()` was deprecated in OpenSSL 3.0.

COPYRIGHT

Copyright 2000-2022 The OpenSSL Project Authors. All Rights Reserved.
Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file `LICENSE` in the source distribution or at
<<https://www.openssl.org/source/license.html>>.

