



*Full credit is given to the above companies including the OS that this PDF file was generated!*

***Rocky Enterprise Linux 9.2 Manual Pages on command 'SSL\_use\_cert\_and\_key.3ossl'***

***\$ man SSL\_use\_cert\_and\_key.3ossl***

SSL\_CTX\_USE\_CERTIFICATE(3ossl) OpenSSL SSL\_CTX\_USE\_CERTIFICATE(3ossl)

**NAME**

SSL\_CTX\_use\_certificate, SSL\_CTX\_use\_certificate\_ASN1,  
SSL\_CTX\_use\_certificate\_file, SSL\_use\_certificate,  
SSL\_use\_certificate\_ASN1, SSL\_use\_certificate\_file,  
SSL\_CTX\_use\_certificate\_chain\_file, SSL\_use\_certificate\_chain\_file,  
SSL\_CTX\_use\_PrivateKey, SSL\_CTX\_use\_PrivateKey\_ASN1,  
SSL\_CTX\_use\_PrivateKey\_file, SSL\_CTX\_use\_RSAPrivateKey,  
SSL\_CTX\_use\_RSAPrivateKey\_ASN1, SSL\_CTX\_use\_RSAPrivateKey\_file,  
SSL\_use\_PrivateKey\_file, SSL\_use\_PrivateKey\_ASN1, SSL\_use\_PrivateKey,  
SSL\_use\_RSAPrivateKey, SSL\_use\_RSAPrivateKey\_ASN1,  
SSL\_use\_RSAPrivateKey\_file, SSL\_CTX\_check\_private\_key,  
SSL\_check\_private\_key, SSL\_CTX\_use\_cert\_and\_key, SSL\_use\_cert\_and\_key -  
load certificate and key data

**SYNOPSIS**

#include <openssl/ssl.h>

```

int SSL_CTX_use_certificate(SSL_CTX *ctx, X509 *x);
int SSL_CTX_use_certificate_ASN1(SSL_CTX *ctx, int len, const unsigned char *d);
int SSL_CTX_use_certificate_file(SSL_CTX *ctx, const char *file, int type);
int SSL_use_certificate(SSL *ssl, X509 *x);
int SSL_use_certificate_ASN1(SSL *ssl, const unsigned char *d, int len);
int SSL_use_certificate_file(SSL *ssl, const char *file, int type);

int SSL_CTX_use_certificate_chain_file(SSL_CTX *ctx, const char *file);
int SSL_use_certificate_chain_file(SSL *ssl, const char *file);

int SSL_CTX_use_PrivateKey(SSL_CTX *ctx, EVP_PKEY *pkey);
int SSL_CTX_use_PrivateKey_ASN1(int pk, SSL_CTX *ctx, const unsigned char *d,
                                long len);
int SSL_CTX_use_PrivateKey_file(SSL_CTX *ctx, const char *file, int type);
int SSL_CTX_use_RSAPrivateKey(SSL_CTX *ctx, RSA *rsa);
int SSL_CTX_use_RSAPrivateKey_ASN1(SSL_CTX *ctx, const unsigned char *d, long len);
int SSL_CTX_use_RSAPrivateKey_file(SSL_CTX *ctx, const char *file, int type);
int SSL_use_PrivateKey(SSL *ssl, EVP_PKEY *pkey);
int SSL_use_PrivateKey_ASN1(int pk, SSL *ssl, const unsigned char *d, long len);
int SSL_use_PrivateKey_file(SSL *ssl, const char *file, int type);
int SSL_use_RSAPrivateKey(SSL *ssl, RSA *rsa);
int SSL_use_RSAPrivateKey_ASN1(SSL *ssl, const unsigned char *d, long len);
int SSL_use_RSAPrivateKey_file(SSL *ssl, const char *file, int type);

int SSL_CTX_check_private_key(const SSL_CTX *ctx);
int SSL_check_private_key(const SSL *ssl);

int SSL_CTX_use_cert_and_key(SSL_CTX *ctx, X509 *x, EVP_PKEY *pkey, STACK_OF(X509) *chain, int override);
int SSL_use_cert_and_key(SSL *ssl, X509 *x, EVP_PKEY *pkey, STACK_OF(X509) *chain, int override);

```

## DESCRIPTION

These functions load the certificates and private keys into the SSL\_CTX

or SSL object, respectively.

The `SSL_CTX_*` class of functions loads the certificates and keys into the `SSL_CTX` object `ctx`. The information is passed to SSL objects `ssl` created from `ctx` with `SSL_new(3)` by copying, so that changes applied to `ctx` do not propagate to already existing SSL objects.

The `SSL_*` class of functions only loads certificates and keys into a specific SSL object. The specific information is kept, when `SSL_clear(3)` is called for this SSL object.

`SSL_CTX_use_certificate()` loads the certificate `x` into `ctx`,  
`SSL_use_certificate()` loads `x` into `ssl`. The rest of the certificates needed to form the complete certificate chain can be specified using the `SSL_CTX_add_extra_chain_cert(3)` function.

`SSL_CTX_use_certificate_ASN1()` loads the ASN1 encoded certificate from the memory location `d` (with length `len`) into `ctx`,  
`SSL_use_certificate_ASN1()` loads the ASN1 encoded certificate into `ssl`.

`SSL_CTX_use_certificate_file()` loads the first certificate stored in file into `ctx`. The formatting type of the certificate must be specified from the known types `SSL_FILETYPE_PEM`, `SSL_FILETYPE_ASN1`.

`SSL_use_certificate_file()` loads the certificate from file into `ssl`.

See the NOTES section on why `SSL_CTX_use_certificate_chain_file()` should be preferred.

`SSL_CTX_use_certificate_chain_file()` loads a certificate chain from file into `ctx`. The certificates must be in PEM format and must be sorted starting with the subject's certificate (actual client or server certificate), followed by intermediate CA certificates if applicable, and ending at the highest level (root) CA.

`SSL_use_certificate_chain_file()` is similar except it loads the

certificate chain into ssl.

SSL\_CTX\_use\_PrivateKey() adds pkey as private key to ctx.

SSL\_CTX\_use\_RSAPrivateKey() adds the private key rsa of type RSA to ctx. SSL\_use\_PrivateKey() adds pkey as private key to ssl;

SSL\_use\_RSAPrivateKey() adds rsa as private key of type RSA to ssl. If a certificate has already been set and the private key does not belong to the certificate an error is returned. To change a

[certificate/private-key] pair, the new certificate needs to be set first with SSL\_use\_certificate() or SSL\_CTX\_use\_certificate() before setting the private key with SSL\_CTX\_use\_PrivateKey() or SSL\_use\_PrivateKey().

SSL\_CTX\_use\_cert\_and\_key() and SSL\_use\_cert\_and\_key() assign the X.509 certificate x, private key key, and certificate chain onto the corresponding ssl or ctx. The pkey argument must be the private key of the X.509 certificate x. If the override argument is 0, then x, pkey and chain are set only if all were not previously set. If override is non-0, then the certificate, private key and chain certs are always set. If pkey is NULL, then the public key of x is used as the private key. This is intended to be used with hardware (via the ENGINE interface) that stores the private key securely, such that it cannot be accessed by OpenSSL. The reference count of the public key is incremented (twice if there is no private key); it is not copied nor duplicated. This allows all private key validations checks to succeed without an actual private key being assigned via

SSL\_CTX\_use\_PrivateKey(), etc.

SSL\_CTX\_use\_PrivateKey\_ASN1() adds the private key of type pk stored at memory location d (length len) to ctx.

SSL\_CTX\_use\_RSAPrivateKey\_ASN1() adds the private key of type RSA stored at memory location d (length len) to ctx.

SSL\_use\_PrivateKey\_ASN1() and SSL\_use\_RSAPrivateKey\_ASN1() add the

private key to ssl.

`SSL_CTX_use_PrivateKey_file()` adds the first private key found in file to ctx. The formatting type of the private key must be specified from the known types `SSL_FILETYPE_PEM`, `SSL_FILETYPE_ASN1`.

`SSL_CTX_use_RSAPrivateKey_file()` adds the first private RSA key found in file to ctx. `SSL_use_PrivateKey_file()` adds the first private key found in file to ssl; `SSL_use_RSAPrivateKey_file()` adds the first private RSA key found to ssl.

`SSL_CTX_check_private_key()` checks the consistency of a private key with the corresponding certificate loaded into ctx. If more than one key/certificate pair (RSA/DSA) is installed, the last item installed will be checked. If e.g. the last item was a RSA certificate or key, the RSA key/certificate pair will be checked. `SSL_check_private_key()` performs the same check for ssl. If no key/certificate was explicitly added for this ssl, the last item added into ctx will be checked.

## NOTES

The internal certificate store of OpenSSL can hold several private key/certificate pairs at a time. The certificate used depends on the cipher selected, see also `SSL_CTX_set_cipher_list(3)`.

When reading certificates and private keys from file, files of type `SSL_FILETYPE_ASN1` (also known as DER, binary encoding) can only contain one certificate or private key, consequently

`SSL_CTX_use_certificate_chain_file()` is only applicable to PEM formatting. Files of type `SSL_FILETYPE_PEM` can contain more than one item.

`SSL_CTX_use_certificate_chain_file()` adds the first certificate found in the file to the certificate store. The other certificates are added to the store of chain certificates using `SSL_CTX_add1_chain_cert(3)`.

Note: versions of OpenSSL before 1.0.2 only had a single certificate chain store for all certificate types, OpenSSL 1.0.2 and later have a separate chain store for each type.

`SSL_CTX_use_certificate_chain_file()` should be used instead of the `SSL_CTX_use_certificate_file()` function in order to allow the use of complete certificate chains even when no trusted CA storage is used or when the CA issuing the certificate shall not be added to the trusted CA storage.

If additional certificates are needed to complete the chain during the TLS negotiation, CA certificates are additionally looked up in the locations of trusted CA certificates, see `SSL_CTX_load_verify_locations(3)`.

The private keys loaded from file can be encrypted. In order to successfully load encrypted keys, a function returning the passphrase must have been supplied, see `SSL_CTX_set_default_passwd_cb(3)`. (Certificate files might be encrypted as well from the technical point of view, it however does not make sense as the data in the certificate is considered public anyway.)

All of the functions to set a new certificate will replace any existing certificate of the same type that has already been set. Similarly all of the functions to set a new private key will replace any private key that has already been set. Applications should call `SSL_CTX_check_private_key(3)` or `SSL_check_private_key(3)` as appropriate after loading a new certificate and private key to confirm that the certificate and key match.

## RETURN VALUES

On success, the functions return 1. Otherwise check out the error stack to find out the reason.

## SEE ALSO

ssl(7), SSL\_new(3), SSL\_clear(3), SSL\_CTX\_load\_verify\_locations(3),  
SSL\_CTX\_set\_default\_passwd\_cb(3), SSL\_CTX\_set\_cipher\_list(3),  
SSL\_CTX\_set\_client\_CA\_list(3), SSL\_CTX\_set\_client\_cert\_cb(3),  
SSL\_CTX\_add\_extra\_chain\_cert(3)

## COPYRIGHT

Copyright 2000-2022 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use  
this file except in compliance with the License. You can obtain a copy  
in the file LICENSE in the source distribution or at  
<<https://www.openssl.org/source/license.html>>.

3.0.7                    2023-07-13    SSL\_CTX\_USE\_CERTIFICATE(3ossl)