

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'du.1'

\$ man du.1

DU(1)

User Commands

DU(1)

NAME

du - estimate file space usage

SYNOPSIS

du [OPTION]... [FILE]...

du [OPTION]... --files0-from=F

DESCRIPTION

Summarize disk usage of the set of FILEs, recursively for directories.

Mandatory arguments to long options are mandatory for short options

too.

-0, --null

end each output line with NUL, not newline

-a, --all

write counts for all files, not just directories

--apparent-size

print apparent sizes, rather than disk usage; although the ap? parent size is usually smaller, it may be larger due to holes in

('sparse') files, internal fragmentation, indirect blocks, and

the like

-B, --block-size=SIZE

scale sizes by SIZE before printing them; e.g., '-BM' prints sizes in units of 1,048,576 bytes; see SIZE format below

-b, --bytes

equivalent to '--apparent-size --block-size=1'

-c, --total

produce a grand total

-D, --dereference-args

dereference only symlinks that are listed on the command line

-d, --max-depth=N

print the total for a directory (or file, with --all) only if it

is N or fewer levels below the command line argument;

--max-depth=0 is the same as --summarize

--files0-from=F

summarize disk usage of the NUL-terminated file names specified in file F; if F is -, then read names from standard input

-H equivalent to --dereference-args (-D)

-h, --human-readable

print sizes in human readable format (e.g., 1K 234M 2G)

--inodes

list inode usage information instead of block usage

-k like --block-size=1K

-L, --dereference

dereference all symbolic links

-I, --count-links

count sizes many times if hard linked

-m like --block-size=1M

-P, --no-dereference

don't follow any symbolic links (this is the default)

-S, --separate-dirs

for directories do not include size of subdirectories

--si like -h, but use powers of 1000 not 1024

-s, --summarize

display only a total for each argument

-t, --threshold=SIZE

exclude entries smaller than SIZE if positive, or entries greater than SIZE if negative

--time show time of the last modification of any file in the directory,

or any of its subdirectories

--time=WORD

show time as WORD instead of modification time: atime, access, use, ctime or status

--time-style=STYLE

show times using STYLE, which can be: full-iso, long-iso, iso, or +FORMAT; FORMAT is interpreted like in 'date'

-X, --exclude-from=FILE

exclude files that match any pattern in FILE

--exclude=PATTERN

exclude files that match PATTERN

-x, --one-file-system

skip directories on different file systems

--help display this help and exit

--version

output version information and exit

Display values are in units of the first available SIZE from

--block-size, and the DU_BLOCK_SIZE, BLOCK_SIZE and BLOCKSIZE environ?

ment variables. Otherwise, units default to 1024 bytes (or 512 if

POSIXLY CORRECT is set).

The SIZE argument is an integer and optional unit (example: 10K is

10*1024). Units are K,M,G,T,P,E,Z,Y (powers of 1024) or KB,MB,...

(powers of 1000). Binary prefixes can be used, too: KiB=K, MiB=M, and

so on.

PATTERNS

PATTERN is a shell pattern (not a regular expression). The pattern?

matches any one character, whereas * matches any string (composed of

zero, one or multiple characters). For example, *.o will match any files whose names end in .o. Therefore, the command

du --exclude='*.o'

will skip all files and subdirectories ending in .o (including the file .o itself).

AUTHOR

Written by Torbjorn Granlund, David MacKenzie, Paul Eggert, and Jim Meyering.

REPORTING BUGS

GNU coreutils online help: https://www.gnu.org/software/coreutils/>
Report any translation bugs to https://translationproject.org/team/>

COPYRIGHT

Copyright ? 2020 Free Software Foundation, Inc. License GPLv3+: GNU

GPL version 3 or later https://gnu.org/licenses/gpl.html.

This is free software: you are free to change and redistribute it.

There is NO WARRANTY, to the extent permitted by law.

or available locally via: info '(coreutils) du invocation'

SEE ALSO

Full documentation https://www.gnu.org/software/coreutils/du

GNU coreutils 8.32 Ja

January 2023

DU(1)