



Rocky Enterprise Linux 9.2 Manual Pages on command 'initstate_r.3'

\$ man initstate_r.3

RANDOM_R(3) Linux Programmer's Manual RANDOM_R(3)

NAME

random_r, srandom_r, initstate_r, setstate_r - reentrant random number generator

SYNOPSIS

```
#include <stdlib.h>

int random_r(struct random_data *buf, int32_t *result);

int srandom_r(unsigned int seed, struct random_data *buf);

int initstate_r(unsigned int seed, char *statebuf,
                size_t statelen, struct random_data *buf);

int setstate_r(char *statebuf, struct random_data *buf);
```

Feature Test Macro Requirements for glibc (see feature_test_macros(7)):

```
random_r(), srandom_r(), initstate_r(), setstate_r():

/* Glibc since 2.19: */ _DEFAULT_SOURCE

|| /* Glibc versions <= 2.19: */ _SVID_SOURCE || _BSD_SOURCE
```

DESCRIPTION

These functions are the reentrant equivalents of the functions described in random(3). They are suitable for use in multithreaded pro-

grams where each thread needs to obtain an independent, reproducible sequence of random numbers.

The `random_r()` function is like `random(3)`, except that instead of using state information maintained in a global variable, it uses the state information in the argument pointed to by `buf`, which must have been previously initialized by `initstate_r()`. The generated random number is returned in the argument result.

The `srandom_r()` function is like `srandom(3)`, except that it initializes the seed for the random number generator whose state is maintained in the object pointed to by `buf`, which must have been previously initialized by `initstate_r()`, instead of the seed associated with the global state variable.

The `initstate_r()` function is like `initstate(3)` except that it initializes the state in the object pointed to by `buf`, rather than initializing the global state variable. Before calling this function, the `buf.state` field must be initialized to `NULL`. The `initstate_r()` function records a pointer to the `statebuf` argument inside the structure pointed to by `buf`. Thus, `statebuf` should not be deallocated so long as `buf` is still in use. (So, `statebuf` should typically be allocated as a static variable, or allocated on the heap using `malloc(3)` or similar.)

The `setstate_r()` function is like `setstate(3)` except that it modifies the state in the object pointed to by `buf`, rather than modifying the global state variable. `state` must first have been initialized using `initstate_r()` or be the result of a previous call of `setstate_r()`.

RETURN VALUE

All of these functions return 0 on success. On error, -1 is returned, with `errno` set to indicate the cause of the error.

ERRORS

EINVAL A state array of less than 8 bytes was specified to `initstate_r()`.

EINVAL The `statebuf` or `buf` argument to `setstate_r()` was `NULL`.

EINVAL The `buf` or result argument to `random_r()` was `NULL`.

ATTRIBUTES

For an explanation of the terms used in this section, see at?

tributes(7).

??

?Interface ? Attribute ? Value ?

??

?random_r(), srandom_r(), ? Thread safety ? MT-Safe race:buf ?

?initstate_r(), setstate_r() ? ? ?

??

CONFORMING TO

These functions are nonstandard glibc extensions.

BUGS

The initstate_r() interface is confusing. It appears that the ran?
dom_data type is intended to be opaque, but the implementation requires
the user to either initialize the buf.state field to NULL or zero out
the entire structure before the call.

SEE ALSO

drand48(3), rand(3), random(3)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A
description of the project, information about reporting bugs, and the
latest version of this page, can be found at
<https://www.kernel.org/doc/man-pages/>.

GNU 2017-09-15 RANDOM_R(3)