

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'pacat.1'

pacat(1)

\$ man	pacat.1	

pacat(1)	General Commands Manual

# NAME

pacat - Play back or record raw or encoded audio streams on a PulseAu?

dio sound server

# SYNOPSIS

paplay [options] [FILE]

parecord [options] [FILE]

pacat [options] [FILE]

parec [options] [FILE]

pamon [options] [FILE]

pacat --help

pacat --version

# DESCRIPTION

pacat is a simple tool for playing back or capturing raw or encoded au?

dio files on a PulseAudio sound server. It understands all audio file

formats supported by libsndfile.

# OPTIONS

Show help.

## --version

Show version information.

-r | --record

Capture audio data and write it to the specified file or to STD?

 $\ensuremath{\mathsf{OUT}}$  if none is specified. If the tool is called under the name

parec this is the default.

-p | --playback

Read audio data from the specified file or STDIN if none is specified, and play it back. If the tool is called under the

name pacat this is the default.

-v | --verbose

Enable verbose operation. Dumps the current playback time to

STDERR during playback/capturing.

-s | --server=SERVER

Choose the server to connect to.

-d | --device=SINKORSOURCE

Specify the symbolic name of the sink/source to play/record this

stream on/from.

## --monitor-stream=INDEX

Record from the sink input with index INDEX.

## -n | --client-name=NAME

Specify the client name paplay shall pass to the server when

connecting.

--stream-name=NAME

Specify the stream name paplay shall pass to the server when

creating the stream.

--volume=VOLUME

Specify the initial playback volume to use. Choose a value be?

tween 0 (silent) and 65536 (100% volume).

# --rate=SAMPLERATE

Capture or play back audio with the specified sample rate. De?

faults to 44100 Hz.

Capture or play back audio with the specified sample format. See https://www.freedesktop.org/wiki/Software/PulseAudio/Documenta? tion/User/SupportedAudioFormats/ for supported values. Defaults to s16ne.

#### --channels=CHANNELS

Capture or play back audio with the specified number of chan? nels. If more than two channels are used it is recommended to use the --channel-map option below. Defaults to 2.

### --channel-map=CHANNELMAP

Explicitly choose a channel map when playing back this stream. The argument should be a comma separated list of channel names: front-left, front-right, mono, front-center, rear-left, rearright, rear-center, lfe, front-left-of-center, front-right-ofcenter, side-left, side-right, top-center, top-front-center, top-front-left, top-front-right, top-rear-left, top-rear-right, top-rear-center, or any of the 32 auxiliary channel names aux0 to aux31.

#### --fix-format

If passed, the sample format of the stream is changed to the na? tive format of the sink the stream is connected to.

#### --fix-rate

If passed, the sampling rate of the stream is changed to the na?

tive rate of the sink the stream is connected to.

#### --fix-channels

If passed, the number of channels and the channel map of the stream is changed to the native number of channels and the na? tive channel map of the sink the stream is connected to.

#### --no-remix

Never upmix or downmix channels.

#### --no-remap

Never remap channels. Instead of mapping channels by their name

this will match them solely by their index/order.

Explicitly configure the latency, with a time specified in bytes in the selected sample format. If left out the server will pick the latency, usually relatively high for power saving reasons. Use either this option or --latency-msec, but not both.

### --latency-msec=MSEC

Explicitly configure the latency, with a time specified in mil? liseconds. If left out the server will pick the latency, usually relatively high for power saving reasons. Use either this option or --latency, but not both.

### --process-time=BYTES

Explicitly configure the process time, with a time specified in bytes in the selected sample format. If left out the server will pick the process time. Use either this option or --process-timemsec, but not both.

#### --process-time-msec=MSEC

Explicitly configure the process time, with a time specified in milliseconds. If left out the server will pick the process time.

Use either this option or --process-time, but not both.

### --property=PROPERTY=VALUE

Attach a property to the client and stream. May be used multiple times

--raw Play/record raw audio data. This is the default if this program

is invoked as pacat, parec or pamon.

## --file-format[=FFORMAT]

Play/record encoded audio data in the file format specified.

This is the default if this program is invoked as paplay and parecord.

--list-file-formats

List supported file formats.

### LIMITATIONS

Due to a limitation in libsndfile paplay currently does not always set

the correct channel mapping for playback of multichannel (i.e. sur?

round) audio files, even if the channel mapping information is avail? able in the audio file.

# AUTHORS

The PulseAudio Developers <pulseaudio-discuss (at) lists (dot) freedesktop (dot) org>; PulseAudio is available from http://pulseau? dio.org/

## SEE ALSO

pulseaudio(1), pactl(1)

Manuals User pacat(1)