



Linux Ubuntu 26.04 Manual Pages on command 'XtAsprintf.3'

\$ man XtAsprintf.3

XtMalloc(3)

XT FUNCTIONS

XtMalloc(3)

NAME _____

XtMalloc, XtCalloc, XtRealloc, XtFree, XtNew, XtNewString - memory management functions

SYNTAX

```
#include <X11/Intrinsic.h>
```

```
char *XtMalloc(Cardinal size);
```

```
char *XtCalloc(Cardinal num, Cardinal size);
```

```
char *XtRealloc(char *ptr, Cardinal num);
```

```
void XtFree(char *ptr);
```

```
type *XtNew(type);
```

```
String XtNewString(String string);
```

```
Cardinal XtAsprintf(char **new_string, const char *format, ...);
```

ARGUMENTS

num	Specifies the number of bytes or array elements.
-----	--

ptr Specifies a pointer to the old storage or to the block of storage that is to be freed.

size Specifies the size of an array element (in bytes) or the number of bytes desired.

string Specifies a previously declared string.

type	Specifies a previously declared data type.
------	--

new_string

Specifies a pointer to write a newly allocated string to.

format Specifies a formatting string as defined by `sprintf(3c)`

DESCRIPTION

The `XtMalloc` function returns a pointer to a block of storage of at least the specified size bytes. If there is insufficient memory to allocate the new block, `XtMalloc` calls `XtErrorMsg`.

The `XtCalloc` function allocates space for the specified number of array elements of the specified size and initializes the space to zero. If there is insufficient memory to allocate the new block, `XtCalloc` calls `XtErrorMsg`.

The `XtRealloc` function changes the size of a block of storage (possibly moving it). Then, it copies the old contents (or as much as will fit) into the new block and frees the old block. If there is insufficient memory to allocate the new block, `XtRealloc` calls `XtErrorMsg`. If `ptr` is `NULL`, `XtRealloc` allocates the new storage without copying the old contents; that is, it simply calls `XtMalloc`.

The `XtFree` function returns storage and allows it to be reused. If `ptr` is `NULL`, `XtFree` returns immediately.

`XtNew` returns a pointer to the allocated storage. If there is insufficient memory to allocate the new block, `XtNew` calls `XtErrorMsg`. `XtNew` is a convenience macro that calls `XtMalloc` with the following arguments specified:

```
((type *) XtMalloc((unsigned) sizeof(type)))
```

`XtNewString` returns a pointer to a new string which is a duplicate of `string`. If there is insufficient memory to allocate the new block, or the argument is `NULL`, `XtNewString` returns `NULL`. The memory can be freed with `XtFree`.

The `XtAsprintf` function allocates space for a string large enough to hold the string specified by the `sprintf(3c)` format pattern when used with the remaining arguments, and fills it with the formatted results. The address of the allocated string is placed into the pointer passed as `ret`. The length of the string (not including the terminating null byte) is returned. If there is insufficient memory to allocate the new block, `XtAsprintf` calls `XtErrorMsg`.

SEE ALSO

X Toolkit Intrinsic - C Language Interface

Xlib - C Language X Interface

X Version 11

libXt 1.2.1

XtMalloc(3)