



Linux Ubuntu 26.04 Manual Pages on command 'jcmd.1'

\$ man jcmd.1

JCMD(1)

JDK Commands

JCMD(1)

NAME

jcmd - send diagnostic command requests to a running Java Virtual Machine (JVM)

SYNOPSIS

jcmd [pid | main-class] command... | PerfCounter.print | -f filename

jcmd [-l]

jcmd -h

pid When used, the jcmd utility sends the diagnostic command request to the process ID for the Java process.

main-class

When used, the jcmd utility sends the diagnostic command request to all Java processes with the specified name of the main class.

command

The command must be a valid jcmd command for the selected JVM. The list of available commands for jcmd is obtained by running the help command (jcmd pid help) where pid is the process ID for the running Java process.

Perfcounter.print

Prints the performance counters exposed by the specified Java process.

-f filename

Reads and executes commands from a specified file, filename.

-l Displays the list of Java Virtual Machine process identifiers that are not running in a separate docker process along with the main class and command-line arguments that were used to launch the process. If the JVM is in a docker process, you must use

tools such as ps to look up the PID.

Note:

Using jcmd without arguments is the same as using jcmd -l.

-h Displays the jcmd utility's command-line help.

DESCRIPTION

The jcmd utility is used to send diagnostic command requests to the JVM. It must be used on the same machine on which the JVM is running, and have the same effective user and group identifiers that were used to launch the JVM. Each diagnostic command has its own set of options and arguments. To display the description, syntax, and a list of available options and arguments for a diagnostic command, use the name of the command as the argument. For example:

```
jcmd pid help command
```

If arguments contain spaces, then you must surround them with single or double quotation marks (' or "). In addition, you must escape single or double quotation marks with a backslash (\) to prevent the operating system shell from processing quotation marks. Alternatively, you can surround these arguments with single quotation marks and then with double quotation marks (or with double quotation marks and then with single quotation marks).

If you specify the process identifier (pid) or the main class (main-class) as the first argument, then the jcmd utility sends the diagnostic command request to the Java process with the specified identifier or to all Java processes with the specified name of the main class.

You can also send the diagnostic command request to all available Java processes by specifying 0 as the process identifier.

COMMANDS FOR JCMD

The command must be a valid jcmd diagnostic command for the selected JVM. The list of available commands for jcmd is obtained by running the help command (jcmd pid help) where pid is the process ID for a running Java process. If the pid is 0, commands will be sent to all Java processes. The main class argument will be used to match, either partially or fully, the class used to start Java. If no options are given, it lists the running Java process identifiers that are not in separate docker processes along with the main class and command-line arguments that were used to launch the process (the same as using -l).

jcmd commands may take options and arguments. Options are specified using either key or key=value syntax. Arguments are given as just a value, never name=value.

The following commands are available:

help [options] [arguments]

For more information about a specific command.

arguments:

? command name: The name of the command for which we want help (STRING, no default value)

Note:

The following options must be specified using either key or key=value syntax.

options:

? -all: (Optional) Show help for all commands (BOOLEAN, false) .

Compiler.CodeHeap_Analytics [function] [granularity]

Print CodeHeap analytics

Impact: Low: Depends on code heap size and content. Holds CodeCache_lock during analysis step, usually sub-second duration.

arguments:

? function: (Optional) Function to be performed (aggregate, UsedSpace, FreeSpace, MethodCount, MethodSpace, MethodAge, MethodNames, discard (STRING, all)

? granularity: (Optional) Detail level - smaller value -> more detail (INT, 4096)

Compiler.codecache

Prints code cache layout and bounds.

Impact: Low

Compiler.codelist

Prints all compiled methods in code cache that are alive.

Impact: Medium

Compiler.directives_add arguments

Adds compiler directives from a file.

Impact: Low

arguments:

? filename: The name of the directives file (STRING, no default value)

Compiler.directives_clear

Remove all compiler directives.

Impact: Low

Compiler.directives_print

Prints all active compiler directives.

Impact: Low

Compiler.directives_remove

Remove latest added compiler directive.

Impact: Low

Compiler.memory [options]

Print compilation footprint

Impact: Medium: Pause time depends on number of compiled methods

Note:

The options must be specified using either key or key=value syntax.

options:

? -H: (Optional) Human readable format (BOOLEAN, false)

? -s: (Optional) Minimum memory size (MEMORY SIZE, 0)

Compiler.perfmap [arguments] (Linux only)

Write map file for Linux perf tool.

Impact: Low

arguments:

? filename: (Optional) The name of the map file. If %p is specified in the filename, it is expanded to the JVM's PID. (FILE, "/tmp/perf-%p.map")

Compiler.queue

Prints methods queued for compilation.

Impact: Low

GC.class_histogram [options]

Provides statistics about the Java heap usage.

Impact: High --- depends on Java heap size and content.

Note:

The options must be specified using either key or key=value syntax.

options:

? -all: (Optional) Inspects all objects, including unreachable objects (BOOLEAN, false)

? -parallel: (Optional) Number of parallel threads to use for heap inspection. 0 (the default) means let the VM determine the number of threads to use. 1 means use one thread (disable parallelism). For any other value the VM will try to use the specified number of threads, but might use fewer. (INT, 0)

GC.finalizer_info

Provides information about the Java finalization queue.

Impact: Medium

GC.heap_dump [options] filename

Generates a HPROF format dump of the Java heap.

Impact: High --- depends on the Java heap size and content. Request a full GC unless the -all option is specified.

Note:

The following options must be specified using either key or key=value syntax.

options:

? -all: (Optional) Dump all objects, including unreachable objects (BOOLEAN, false)

? -gz: (Optional) If specified, the heap dump is written in gzipped format using the given compression level. 1 (recommended) is the fastest, 9 the strongest compression. (INT, 1)

? -overwrite: (Optional) If specified, the dump file will be overwritten if it exists (BOOLEAN, false)

? -parallel: (Optional) Number of parallel threads to use for heap dump. The VM will try to use the specified number of threads, but might use fewer. (INT, 1)

arguments:

? filename: The name of the dump file. If %p is specified in the filename, it is expanded to the JVM's PID. (FILE, no default value)

GC.heap_info

Provides generic Java heap information.

Impact: Medium

GC.run Calls java.lang.System.gc().

Impact: Medium --- depends on the Java heap size and content.

GC.run_finalization

Calls java.lang.System.runFinalization().

Impact: Medium --- depends on the Java content.

JFR.check [options]

Show information about a running flight recording

Impact: Low

Note:

The options must be specified using either key or key=value syntax. If no parameters are entered, information for all active recordings is shown.

options:

? name: (Optional) Name of the flight recording. (STRING, no default value)

? verbose: (Optional) Flag for printing the event settings for the recording
(BOOLEAN, false)

JFR.configure [options]

Set the parameters for a flight recording

Impact: Low

Note:

The options must be specified using either key or key=value syntax. If no parameters are entered, the current settings are displayed.

options:

? dumppath: (Optional) Path to the location where a recording file is written in case the VM runs into a critical error, such as a system crash. (STRING, The default location is the current directory)

? globalbuffercount: (Optional) Number of global buffers. This option is a legacy option: change the memorysize parameter to alter the number of global buffers. This value cannot be changed once JFR has been initialized. (STRING, default determined by the value for memorysize)

? globalbuffersize: (Optional) Size of the global buffers, in bytes. This option is a legacy option: change the memorysize parameter to alter the size of the global buffers. This value cannot be changed once JFR has been initialized. (STRING, default determined by the value for memorysize)

? maxchunksize: (Optional) Maximum size of an individual data chunk in bytes if one of the following suffixes is not used: 'm' or 'M' for megabytes OR 'g' or 'G' for gigabytes. This value cannot be changed once JFR has been initialized. (STRING, 12M)

? memorysize: (Optional) Overall memory size, in bytes if one of the following suffixes is not used: 'm' or 'M' for megabytes OR 'g' or 'G' for gigabytes. This value cannot be changed once JFR has been initialized. (STRING, 10M)

? repositorypath: (Optional) Path to the location where recordings are stored until they are written to a permanent file. (STRING, The default location is the tempo?

rary directory for the operating system. On Linux operating systems, the temporary directory is /tmp. On Windows, the temporary directory is specified by the TMP environment variable.)

? preserve-repository={true|false} : Specifies whether files stored in the disk repository should be kept after the JVM has exited. If false, files are deleted.

By default, this parameter is disabled.

? stackdepth: (Optional) Stack depth for stack traces. Setting this value greater than the default of 64 may cause a performance degradation. This value cannot be changed once JFR has been initialized. (LONG, 64)

? thread_buffer_size: (Optional) Local buffer size for each thread in bytes if one of the following suffixes is not used: 'k' or 'K' for kilobytes or 'm' or 'M' for megabytes. Overriding this parameter could reduce performance and is not recommended. This value cannot be changed once JFR has been initialized. (STRING, 8k)

? samplethreads: (Optional) Flag for activating thread sampling. (BOOLEAN, true)

JFR.dump [options]

Write data to a file while a flight recording is running

Impact: Low

Note:

The options must be specified using either key or key=value syntax. No options are required. The recording continues to run after the data is written.

options:

? begin: (Optional) Specify the time from which recording data will be included in the dump file. The format is specified as local time. (STRING, no default value)

? end: (Optional) Specify the time to which recording data will be included in the dump file. The format is specified as local time. (STRING, no default value)

Note: For both begin and end, the time must be in a format that can be read by `java.time.LocalDateTime::parse(STRING)`, `java.time.LocalDateTime::parse(STRING)` or `java.time.Instant::parse(STRING)`. For example, "13:20:15", "2020-03-17T09:00:00" or "2020-03-17T09:00:00Z".

Note: begin and end times correspond to the timestamps found within the recorded information in the flight recording data.

Another option is to use a time relative to the current time that is specified by a negative integer followed by "s", "m" or "h". For example, "-12h", "-15m" or

"-30s"

? filename: (Optional) Name of the file to which the flight recording data is dumped.

If no filename is given, a filename is generated from the PID and the current date.

The filename may also be a directory in which case, the filename is generated from the PID and the current date in the specified directory. If %p and/or %t is specified in the filename, it expands to the JVM's PID and the current timestamp, respectively. (FILE, no default value)

? maxage: (Optional) Length of time for dumping the flight recording data to a file.

(INTEGER followed by 's' for seconds 'm' for minutes or 'h' for hours, no default value)

? maxsize: (Optional) Maximum size for the amount of data to dump from a flight

recording in bytes if one of the following suffixes is not used: 'm' or 'M' for megabytes OR 'g' or 'G' for gigabytes. (STRING, no default value)

? name: (Optional) Name of the recording. If no name is given, data from all recordings

is dumped. (STRING, no default value)

? path-to-gc-roots: (Optional) Flag for saving the path to garbage collection (GC)

roots at the time the recording data is dumped. The path information is useful for finding memory leaks but collecting it can cause the application to pause for a short period of time. Turn on this flag only when you have an application that you suspect has a memory leak. (BOOLEAN, false)

JFR.start [options]

Start a flight recording

Impact: Low

Note:

The options must be specified using either key or key=value syntax. If no parameters are entered, then a recording is started with default values.

options:

? delay: (Optional) Length of time to wait before starting to record (INTEGER fol-

lowed by 's' for seconds 'm' for minutes or 'h' for hours, 0s)

? disk: (Optional) Flag for also writing the data to disk while recording (BOOLEAN,

true)

? dumponexit: (Optional) Flag for writing the recording to disk when the Java Virtual

Machine (JVM) shuts down. If set to 'true' and no value is given for filename, the

recording is written to a file in the directory where the process was started. The file name is a system-generated name that contains the process ID, the recording ID and the current time stamp. (For example: id-1-2019_12_12_10_41.jfr) (BOOLEAN, false)

? duration: (Optional) Length of time to record. Note that 0s means forever (INTEGER followed by 's' for seconds 'm' for minutes or 'h' for hours, 0s)

? filename: (Optional) Name of the file to which the flight recording data is written when the recording is stopped. If no filename is given, a filename is generated from the PID and the current date and is placed in the directory where the process was started. The filename may also be a directory in which case, the filename is generated from the PID and the current date in the specified directory. If %p and/or %t is specified in the filename, it expands to the JVM's PID and the current timestamp, respectively. (FILE, no default value)

? maxage: (Optional) Maximum time to keep the recorded data on disk. This parameter is valid only when the disk parameter is set to true. Note 0s means forever. (INTEGER followed by 's' for seconds 'm' for minutes or 'h' for hours, 0s)

? maxsize: (Optional) Maximum size of the data to keep on disk in bytes if one of the following suffixes is not used: 'm' or 'M' for megabytes OR 'g' or 'G' for gigabytes. This parameter is valid only when the disk parameter is set to 'true'. The value must not be less than the value for the maxchunksize parameter set with the JFR.configure command. (STRING, 0 (no maximum size))

? name: (Optional) Name of the recording. If no name is provided, a name is generated. Make note of the generated name that is shown in the response to the command so that you can use it with other commands. (STRING, system-generated default name)

? path-to-gc-roots: (Optional) Flag for saving the path to garbage collection (GC) roots at the end of a recording. The path information is useful for finding memory leaks but collecting it is time consuming. Turn on this flag only when you have an application that you suspect has a memory leak. If the settings parameter is set to 'profile', then the information collected includes the stack trace from where the potential leaking object was allocated. (BOOLEAN, false)

? settings: (Optional) Name of the settings file that identifies which events to record. To specify more than one file, separate the names with a comma (','). In?

clude the path if the file is not in JAVA-HOME/lib/jfr. The following profiles are included with the JDK in the JAVA-HOME/lib/jfr directory: 'default.jfc': collects a predefined set of information with low overhead, so it has minimal impact on performance and can be used with recordings that run continuously; 'profile.jfc': Provides more data than the 'default.jfc' profile, but with more overhead and impact on performance. Use this configuration for short periods of time when more information is needed. Use none to start a recording without a predefined configuration file. (STRING, JAVA-HOME/lib/jfr/default.jfc)

Event settings and .jfc options can be specified using the following syntax:

? option: (Optional) Specifies the option value to modify. To list available options, use the JAVA_HOME/bin/jfr tool.

? event-setting: (Optional) Specifies the event setting value to modify. Use the form: <event-name>#<setting-name>=<value> To add a new event setting, prefix the event name with '+'.

You can specify values for multiple event settings and .jfc options by separating them with a whitespace. In case of a conflict between a parameter and a .jfc option, the parameter will take precedence. The whitespace delimiter can be omitted for timespan values, i.e. 20ms. For more information about the settings syntax, see Javadoc of the jdk.jfr package.

JFR.stop [options]

Stop a flight recording

Impact: Low

Note:

The options must be specified using either key or key=value syntax. If no parameters are entered, then no recording is stopped.

options:

? filename: (Optional) Name of the file to which the recording is written when the recording is stopped. If %p and/or %t is specified in the filename, it expands to the JVM's PID and the current timestamp, respectively. If no path is provided, the data from the recording is discarded. (FILE, no default value)

? name: (Optional) Name of the recording (STRING, no default value)

JFR.view [options]

Display event data in predefined views.

Impact: Medium

Note:

The options must be specified using either key or key=value syntax. If no parameters are entered, then a list of available views are displayed.

options:

? cell-height: (Optional) Maximum number of rows in a table cell. (INT, default value depends on the view)

? maxage: (Optional) Length of time for the view to span. (INT followed by 's' for seconds 'm' for minutes or 'h' for hours, default value is 10m)

? maxsize: (Optional) Maximum size for the view to span in bytes if one of the following suffixes is not used: 'm' or 'M' for megabytes OR 'g' or 'G' for gigabytes. (STRING, default value is 32MB)

? truncate: (Optional) Maximum number of rows in a table cell. (INT, default value depends on the view)

? verbose: (Optional) Displays the query that makes up the view. (BOOLEAN, default value is false)

? width: (Optional) The width of the view in characters. (INT, default value depends on the view)

arguments:

? view: Name of the view or event type to display. Use help JFR.view to see a list of available views. (STRING, no default value)

The view parameter can be an event type name. Use JFR.view types to see a list. To display all views, use JFR.view all-views. To display all events, use JFR.view all-events.

JVMTI.agent_load [arguments]

Loads JVMTI native agent.

Impact: Low

arguments:

? library path: Absolute path of the JVMTI agent to load. (STRING, no default value)

? agent option: (Optional) Option string to pass the agent. (STRING, no default value)

JVMTI.data_dump

Signal the JVM to do a data-dump request for JVMTI.

Impact: High

ManagementAgent.start [options]

Starts remote management agent.

Impact: Low --- no impact

Note:

The following options must be specified using either key or key=value syntax.

options:

- ? config.file: (Optional) Sets com.sun.management.config.file (STRING, no default value)
- ? jmxremote.host: (Optional) Sets com.sun.management.jmxremote.host (STRING, no default value)
- ? jmxremote.port: (Optional) Sets com.sun.management.jmxremote.port (STRING, no default value)
- ? jmxremote.rmi.port: (Optional) Sets com.sun.management.jmxremote.rmi.port (STRING, no default value)
- ? jmxremote.ssl: (Optional) Sets com.sun.management.jmxremote.ssl (STRING, no default value)
- ? jmxremote.registry.ssl: (Optional) Sets com.sun.management.jmxremote.registry.ssl (STRING, no default value)
- ? jmxremote.authenticate: (Optional) Sets com.sun.management.jmxremote.authenticate (STRING, no default value)
- ? jmxremote.password.file: (Optional) Sets com.sun.management.jmxremote.password.file (STRING, no default value)
- ? jmxremote.access.file: (Optional) Sets com.sun.management.jmxremote.access.file (STRING, no default value)
- ? jmxremote.login.config: (Optional) Sets com.sun.management.jmxremote.login.config (STRING, no default value)
- ? jmxremote.ssl.enabled.cipher.suites: (Optional) Sets com.sun.management.jmxremote.ssl.enabled.cipher.suites (STRING, no default value)
- ? jmxremote.ssl.enabled.cipher.suite: (Optional) Sets com.sun.management.jmxremote.ssl.enabled.cipher.suite (STRING, no default value)
- ? jmxremote.ssl.enabled.protocols: (Optional) Sets com.sun.management.jmxremote.ssl.enabled.protocols (STRING, no default value)
- ? jmxremote.ssl.need.client.auth: (Optional) Sets com.sun.management.jmxremote.ssl.need.client.auth (STRING, no default value)

? jmxremote.ssl.config.file: (Optional) Sets com.sun.management.jmxremote. ssl_con?

fig_file (STRING, no default value)

? jmxremote.autodiscovery: (Optional) Sets com.sun.management.jmxremote.au todiscov?

ery (STRING, no default value)

? jdp.port: (Optional) Sets com.sun.management.jdp.port (INT, no default value)

? jdp.address: (Optional) Sets com.sun.management.jdp.address (STRING, no default value)

? jdp.source_addr: (Optional) Sets com.sun.management.jdp.source_addr (STRING, no default value)

? jdp.ttl: (Optional) Sets com.sun.management.jdp.ttl (INT, no default value)

? jdp.pause: (Optional) Sets com.sun.management.jdp.pause (INT, no default value)

? jdp.name: (Optional) Sets com.sun.management.jdp.name (STRING, no default value)

ManagementAgent.start_local

Starts the local management agent.

Impact: Low --- no impact

ManagementAgent.status

Print the management agent status.

Impact: Low --- no impact

ManagementAgent.stop

Stops the remote management agent.

Impact: Low --- no impact

System.dump_map [options] (Linux only)

Dumps an annotated process memory map to an output file.

Impact: Low

Note:

The following options must be specified using either key or key=value syntax.

options:

? -H: (Optional) Human readable format (BOOLEAN, false)

? -F: (Optional) File path. If %p is specified in the filename, it is expanded to the JVM's PID. (FILE, "vm_memory_map_%p.txt")

System.map [options] (Linux only)

Prints an annotated process memory map of the VM process.

Impact: Low

Note:

The following options must be specified using either key or key=value syntax.

options:

? -H: (Optional) Human readable format (BOOLEAN, false)

System.native_heap_info (Linux only)

Attempts to output information regarding native heap usage through malloc_info(3).

If unsuccessful outputs "Error: " and a reason.

Impact: Low

System.trim_native_heap (Linux only)

Attempts to free up memory by trimming the C-heap.

Impact: Low

Thread.dump_to_file [options] filepath

Dump threads, with stack traces, to a file in plain text or JSON format.

Impact: Medium: Depends on the number of threads.

Note:

The following options must be specified using either key or key=value syntax.

options:

? -overwrite: (Optional) May overwrite existing file (BOOLEAN, false)

? -format: (Optional) Output format ("plain" or "json") (STRING, plain)

arguments:

? filepath: The file path to the output file. If %p is specified in the filename, it is expanded to the JVM's PID. (FILE, no default value)

Thread.print [options]

Prints all threads with stacktraces.

Impact: Medium --- depends on the number of threads.

Note:

The following options must be specified using either key or key=value syntax.

options:

? -e: (Optional) Print extended thread information (BOOLEAN, false)

? -l: (Optional) Prints java.util.concurrent locks (BOOLEAN, false)

Thread.vthread_scheduler

Print the virtual thread scheduler, and the delayed task schedulers that support virtual threads doing timed operations.

Impact: Low

Thread.vthread_pollers

Print the I/O pollers that support virtual threads doing blocking network I/O operations.

Impact: Low

VM.cds [arguments]

Dump a static or dynamic shared archive that includes all currently loaded classes.

Impact: Medium --- pause time depends on number of loaded classes

arguments:

? subcmd: must be either static_dump or dynamic_dump (STRING, no default value)

? filename: (Optional) Name of the shared archive to be dumped. If %p is specified in the filename, it is expanded to the JVM's PID. (FILE, "java_pid%p_<sub?cmd>.jsa")

If dynamic_dump is specified, the target JVM must be started with the JVM option -XX:+RecordDynamicDumpInfo.

VM.class_hierarchy [options] [arguments]

Print a list of all loaded classes, indented to show the class hierarchy. The name of each class is followed by the ClassLoaderData* of its ClassLoader, or "null" if it is loaded by the bootstrap class loader.

Impact: Medium --- depends on the number of loaded classes.

Note:

The following options must be specified using either key or key=value syntax.

options:

? -i: (Optional) Inherited interfaces should be printed. (BOOLEAN, false)

? -s: (Optional) If a classname is specified, print its subclasses in addition to its superclasses. Without this option only the superclasses will be printed. (BOOLEAN, false)

arguments:

? classname: (Optional) The name of the class whose hierarchy should be printed. If not specified, all class hierarchies are printed. (STRING, no default value)

VM.classes [options]

Print all loaded classes

Impact: Medium: Depends on number of loaded classes.

The following options must be specified using either key or key=value syntax.

options:

? -verbose: (Optional) Dump the detailed content of a Java class. Some classes are annotated with flags: F = has, or inherits, a non-empty finalize method, f = has final method, W = methods rewritten, C = marked with @Contended annotation, R = has been redefined, S = is shared class (BOOLEAN, false)

VM.classloader_stats

Print statistics about all ClassLoaders.

Impact: Low

VM.classloaders [options]

Prints classloader hierarchy.

Impact: Medium --- Depends on number of class loaders and classes loaded.

The following options must be specified using either key or key=value syntax.

options:

? show-classes: (Optional) Print loaded classes. (BOOLEAN, false)

? verbose: (Optional) Print detailed information. (BOOLEAN, false)

? fold: (Optional) Show loaders of the same name and class as one. (BOOLEAN, true)

VM.command_line

Print the command line used to start this VM instance.

Impact: Low

VM.dynlibs

Print loaded dynamic libraries.

Impact: Low

VM.events [options]

Print VM event logs

Impact: Low --- Depends on event log size.

options:

Note:

The following options must be specified using either key or key=value syntax.

? log: (Optional) Name of log to be printed. If omitted, all logs are printed.

(STRING, no default value)

? max: (Optional) Maximum number of events to be printed (newest first). If omitted

or zero, all events are printed. (INT, 0)

VM.flags [options]

Print the VM flag options and their current values.

Impact: Low

Note:

The following options must be specified using either key or key=value syntax.

options:

? -all: (Optional) Prints all flags supported by the VM (BOOLEAN, false).

VM.info

Print information about the JVM environment and status.

Impact: Low

VM.log [options]

Lists current log configuration, enables/disables/configures a log output, or rotates all logs.

Impact: Low

options:

Note:

The following options must be specified using either key or key=value syntax.

? output: (Optional) The name or index (#) of output to configure. (STRING, no default value)

? output_options: (Optional) Options for the output. (STRING, no default value)

? what: (Optional) Configures what tags to log. (STRING, no default value)

? decorators: (Optional) Configures which decorators to use. Use 'none' or an empty value to remove all. (STRING, no default value)

? disable: (Optional) Turns off all logging and clears the log configuration. (BOOLEAN, no default value)

? list: (Optional) Lists current log configuration. (BOOLEAN, no default value)

? rotate: (Optional) Rotates all logs. (BOOLEAN, no default value)

VM.metaspace [options]

Prints the statistics for the metaspace

Impact: Medium --- Depends on number of classes loaded.

Note:

The following options must be specified using either key or key=value syntax.

options:

? basic: (Optional) Prints a basic summary (does not need a safepoint). (BOOLEAN, false)

? show-loaders: (Optional) Shows usage by class loader. (BOOLEAN, false)

? show-classes: (Optional) If show-loaders is set, shows loaded classes for each loader. (BOOLEAN, false)

? by-chunktype: (Optional) Break down numbers by chunk type. (BOOLEAN, false)

? by-spacetype: (Optional) Break down numbers by loader type. (BOOLEAN, false)

? vslist: (Optional) Shows details about the underlying virtual space. (BOOLEAN, false)

? chunkfreelist: (Optional) Shows details about global chunk free lists (ChunkManager). (BOOLEAN, false)

? scale: (Optional) Memory usage in which to scale. Valid values are: 1, KB, MB or GB (fixed scale) or "dynamic" for a dynamically chosen scale. (STRING, dynamic)

VM.native_memory [options]

Print native memory usage

Impact: Medium

Note:

The following options must be specified using either key or key=value syntax.

options:

? summary: (Optional) Requests runtime to report current memory summary, which includes total reserved and committed memory, along with memory usage summary by each subsystem. (BOOLEAN, false)

? detail: (Optional) Requests runtime to report memory allocation $\geq$ 1K by each call? site. (BOOLEAN, false)

? baseline: (Optional) Requests runtime to baseline current memory usage, so it can be compared against in later time. (BOOLEAN, false)

? summary.diff: (Optional) Requests runtime to report memory summary comparison against previous baseline. (BOOLEAN, false)

? detail.diff: (Optional) Requests runtime to report memory detail comparison against previous baseline, which shows the memory allocation activities at different call? sites. (BOOLEAN, false)

? statistics: (Optional) Prints tracker statistics for tuning purpose. (BOOLEAN, false)

? scale: (Optional) Memory usage in which scale, KB, MB or GB (STRING, KB)

VM.set_flag [arguments]

Sets VM flag option using the provided value.

Impact: Low

arguments:

? flag name: The name of the flag that you want to set (STRING, no default value)

? string value: (Optional) The value that you want to set (STRING, no default value)

VM.stringtable [options]

Dump string table.

Impact: Medium --- depends on the Java content.

Note:

The following options must be specified using either key or key=value syntax.

options:

? -verbose: (Optional) Dumps the content of each string in the table (BOOLEAN, false)

VM.symboltable [options]

Dump symbol table.

Impact: Medium --- depends on the Java content.

Note:

The following options must be specified using either key or key=value syntax).

options:

? -verbose: (Optional) Dumps the content of each symbol in the table (BOOLEAN, false)

VM.system_properties

Print system properties.

Impact: Low

VM.systemdictionary

Prints the statistics for dictionary hashtable sizes and bucket length.

Impact: Medium

Note:

The following options must be specified using either key or key=value syntax.

options:

? verbose: (Optional) Dump the content of each dictionary entry for all class loaders

(BOOLEAN, false) .

VM.uptime [options]

Print VM uptime.

Impact: Low

Note:

The following options must be specified using either key or key=value syntax.

options:

? -date: (Optional) Adds a prefix with the current date (BOOLEAN, false)

VM.version

Print JVM version information.

Impact: Low

JDK 25.0.3	2026	JCMD(1)
------------	------	---------