



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'swapon.8'***

**\$ man swapon.8**

SWAPON(8)

System Administration

SWAPON(8)

### NAME

swapon, swapoff - enable/disable devices and files for paging and swapping

### SYNOPSIS

swapon [options] [specialfile...]

swapoff [-va] [specialfile...]

### DESCRIPTION

swapon is used to specify devices on which paging and swapping are to take place.

The device or file used is given by the specialfile parameter. It may be of the form -L

label or -U uuid to indicate a device by label or uuid.

Calls to swapon normally occur in the system boot scripts making all swap devices available, so that the paging and swapping activity is interleaved across several devices and files.

swapoff disables swapping on the specified devices and files. When the -a flag is given, swapping is disabled on all known swap devices and files (as found in /proc/swaps or /etc/fstab).

### OPTIONS

-a, --all

All devices marked as "swap" in /etc/fstab are made available, except for those with the "noauto" option. Devices that are already being used as swap are silently skipped.

-d, --discard[=policy]

Enable swap discards, if the swap backing device supports the discard or trim operation. This may improve performance on some Solid State Devices, but often it does

not. The option allows one to select between two available swap discard policies:

**--discard=once**

to perform a single-time discard operation for the whole swap area at swapon; or

**--discard=pages**

to asynchronously discard freed swap pages before they are available for reuse.

If no policy is selected, the default behavior is to enable both discard types. The

/etc/fstab mount options discard, discard=once, or discard=pages may also be used to

enable discard flags.

**-e, --ifexists**

Silently skip devices that do not exist. The /etc/fstab mount option nofail may also

be used to skip non-existing device.

**-f, --fixpgsz**

Reinitialize (exec mkswap) the swap space if its page size does not match that of the current running kernel. mkswap(8) initializes the whole device and does not check for bad blocks.

**-h, --help**

Display help text and exit.

**-L label**

Use the partition that has the specified label. (For this, access to /proc/partitions

is needed.)

**-o, --options opts**

Specify swap options by an fstab-compatible comma-separated string. For example:

swapon -o pri=1,discard=pages,nofail /dev/sda2

The opts string is evaluated last and overrides all other command line options.

**-p, --priority priority**

Specify the priority of the swap device. priority is a value between -1 and 32767.

Higher numbers indicate higher priority. See swapon(2) for a full description of swap priorities. Add pri=value to the option field of /etc/fstab for use with swapon -a.

When no priority is defined, it defaults to -1.

**-s, --summary**

Display swap usage summary by device. Equivalent to cat /proc/swaps. This output

format is DEPRECATED in favour of --show that provides better control on output data.

**--show[=column...]**

Display a definable table of swap areas. See the --help output for a list of available columns.

--output-all

Output all available columns.

--noheadings

Do not print headings when displaying --show output.

--raw

Display --show output without aligning table columns.

--bytes

Display swap size in bytes in --show output instead of in user-friendly units.

-U uuid

Use the partition that has the specified uuid.

-v, --verbose

Be verbose.

-V, --version

Display version information and exit.

## EXIT STATUS

swapoff has the following exit status values since v2.36:

0

success

2

system has insufficient memory to stop swapping (OOM)

4

swapoff syscall failed for another reason

8

non-swapoff syscall system error (out of memory, ...)

16

usage or syntax error

32

all swapoff failed on --all

64

some swapoff succeeded on --all

The command swapoff --all returns 0 (all succeeded), 32 (all failed), or 64 (some failed),

Page 3/5

some succeeded).

+ The old versions before v2.36 has no documented exit status, 0 means success in all versions.

## ENVIRONMENT

`LIBMOUNT_DEBUG=all`

enables libmount debug output.

`LIBBLKID_DEBUG=all`

enables libblkid debug output.

## FILES

`/dev/sd??`

standard paging devices

`/etc/fstab`

ascii filesystem description table

## NOTES

### Files with holes

The swap file implementation in the kernel expects to be able to write to the file directly, without the assistance of the filesystem. This is a problem on files with holes or on copy-on-write files on filesystems like Btrfs.

Commands like `cp(1)` or `truncate(1)` create files with holes. These files will be rejected by `swapon`.

Preallocated files created by `fallocate(1)` may be interpreted as files with holes too depending of the filesystem. Preallocated swap files are supported on XFS since Linux 4.18.

The most portable solution to create a swap file is to use `dd(1)` and `/dev/zero`.

### Btrfs

Swap files on Btrfs are supported since Linux 5.0 on files with `nocow` attribute. See the `btrfs(5)` manual page for more details.

### NFS

Swap over NFS may not work.

### Suspend

`swapon` automatically detects and rewrites a swap space signature with old software suspend data (e.g., `S1SUSPEND`, `S2SUSPEND`, ...). The problem is that if we don't do it, then we get data corruption the next time an attempt at unsuspending is made.

## HISTORY

The swapon command appeared in 4.0BSD.

## SEE ALSO

swapoff(2), swapon(2), fstab(5), init(8), fallocate(1), mkswap(8), mount(8), rc(8)

## REPORTING BUGS

For bug reports, use the issue tracker at <https://github.com/karelzak/util-linux/issues>.

## AVAILABILITY

The swapon command is part of the util-linux package which can be downloaded from Linux

Kernel Archive <<https://www.kernel.org/pub/linux/utils/util-linux/>>.

util-linux 2.37.2

2021-06-02

SWAPON(8)