



## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'XtGetValues.3'***

### **C:\>man XtGetValues.3**

XtSetValues(3)                    XT FUNCTIONS                    XtSetValues(3)

#### NAME

XtSetValues, XtVaSetValues, XtSetSubvalues, XtVaSetSubvalues, XtGetValues, XtVaGetValues, XtGetSubvalues, XtVaGetSubvalues - obtain and set widget resources

#### SYNTAX

```
void XtSetValues(Widget w, ArgList args, Cardinal num_args);
```

```
void XtVaSetValues(Widget w, ...);
```

```
void XtSetSubvalues(XtPointer base, XtResourceList resources, Cardinal num_re?  
                  sources, ArgList args, Cardinal num_args);
```

```
void XtVaSetSubvalues(XtPointer base, XtResourceList resources, Cardinal num_re?  
                  sources, ...);
```

```
void XtGetValues(Widget w, ArgList args, Cardinal num_args);
```

```
void XtVaGetValues(Widget w, ...);
```

```
void XtGetSubvalues(XtPointer base, XtResourceList resources, Cardinal num_re?  
                  sources, ArgList args, Cardinal num_args);
```

```
void XtVaGetSubvalues(XtPointer base, XtResourceList resources, Cardinal num_re?  
                  sources, ...);
```

#### ARGUMENTS

args     Specifies the argument list of name/address pairs that contain the re? source name and either the address into which the resource value is to be stored or their new values.

base     Specifies the base address of the subpart data structure where the re?

sources should be retrieved or written.

`num_args` Specifies the number of arguments in the argument list.

`resources` Specifies the nonwidget resource list or values.

`num_resources`

Specifies the number of resources in the resource list.

`w` Specifies the widget.

... Specifies the variable argument list of name/address pairs that contain the resource name and either the address into which the resource value is to be stored or their new values.

## DESCRIPTION

The `XtSetValues` function starts with the resources specified for the Core widget fields and proceeds down the subclass chain to the widget. At each stage, it writes the new value (if specified by one of the arguments) or the existing value (if no new value is specified) to a new widget data record. `XtSetValues` then calls the `set_values` procedures for the widget in superclass-to-subclass order. If the widget has any non-NULL `set_values_hook` fields, these are called immediately after the corresponding `set_values` procedure. This procedure permits subclasses to set nonwidget data for `XtSetValues`.

If the widget's parent is a subclass of `constraintWidgetClass`, `XtSetValues` also updates the widget's constraints. It starts with the constraint resources specified for `constraintWidgetClass` and proceeds down the subclass chain to the parent's class. At each stage, it writes the new value or the existing value to a new constraint record. It then calls the constraint `set_values` procedures from `constraintWidgetClass` down to the parent's class. The constraint `set_values` procedures are called with widget arguments, as for all `set_values` procedures, not just the constraint record arguments, so that they can make adjustments to the desired values based on full information about the widget.

`XtSetValues` determines if a geometry request is needed by comparing the current widget to the new widget. If any geometry changes are required, it makes the request, and the geometry manager returns `XtGeometryYes`, `XtGeometryAlmost`, or `XtGeometryNo`. If `XtGeometryYes`, `XtSetValues` calls the widget's `resize` procedure. If `XtGeometryNo`, `XtSetValues` resets the geometry fields to their original values. If `XtGeometryAlmost`, `XtSetValues` calls the `set_values_almost` procedure, which deter?

mines what should be done and writes new values for the geometry fields into the new widget. XtSetValues then repeats this process, deciding once more whether the geometry manager should be called.

Finally, if any of the set\_values procedures returned True, XtSetValues causes the widget's expose procedure to be invoked by calling the Xlib XClearArea function on the widget's window.

The XtSetSubvalues function stores resources into the structure identified by base.

The XtGetValues function starts with the resources specified for the core widget fields and proceeds down the subclass chain to the widget. The value field of a passed argument list should contain the address into which to store the corresponding resource value. It is the caller's responsibility to allocate and deallocate this storage according to the size of the resource representation type used within the widget.

If the widget's parent is a subclass of constraintWidgetClass, XtGetValues then fetches the values for any constraint resources requested. It starts with the constraint resources specified for constraintWidgetClass and proceeds down to the subclass chain to the parent's constraint resources. If the argument list contains a resource name that is not found in any of the resource lists searched, the value at the corresponding address is not modified. Finally, if the get\_values\_hook procedures are non-NULL, they are called in superclass-to-subclass order after all the resource values have been fetched by XtGetValues. This permits a subclass to provide nonwidget resource data to XtGetValues.

The XtGetSubvalues function obtains resource values from the structure identified by base.

#### SEE ALSO

X Toolkit Intrinsic - C Language Interface

Xlib - C Language X Interface

X Version 11

libXt 1.1.5

XtSetValues(3)