



Rocky Enterprise Linux 9.2 Manual Pages on command 'gdbus.1'

C:\>man gdbus.1

GDBUS(1) User Commands GDBUS(1)

NAME

gdbus - Tool for working with D-Bus objects

SYNOPSIS

```
gdbus introspect [--system | --session | --address address] --dest bus_name
  --object-path /path/to/object [--xml] [--recurse] [--only-properties]
```

```
gdbus monitor [--system | --session | --address address] --dest bus_name
  [--object-path /path/to/object]
```

```
gdbus call [--system | --session | --address address] --dest bus_name
  --object-path /path/to/object --method org.project.InterfaceName.MethodName
  [--timeout seconds] ARG1 ARG2...
```

```
gdbus emit [--system | --session | --address address] --object-path /path/to/object
  --signal org.project.InterfaceName.SignalName [--dest unique_bus_name] ARG1
  ARG2...
```

```
gdbus wait [--system | --session | --address address] --activate bus_name
  [--timeout seconds] bus_name
```

```
gdbus help
```

DESCRIPTION

gdbus is a simple tool for working with D-Bus objects.

COMMANDS

introspect

Prints out interfaces and property values for a remote object. For this to

work, the owner of the object needs to implement the `org.freedesktop.DBus.Introspectable` interface. If the `--xml` option is used, the returned introspection XML is printed, otherwise a parsed pretty representation is printed. The `--recurse` option can be used to introspect children (and their children and so on) and the `--only-properties` option can be used to only print the interfaces with properties.

monitor

Monitors one or all objects owned by the owner of `bus_name`.

call

Invokes a method on a remote object. Each argument to pass to the method must be specified as a serialized GVariant except that strings do not need explicit quotes. The return values are printed out as serialized GVariant values.

emit

Emits a signal. Each argument to include in the signal must be specified as a serialized GVariant except that strings do not need explicit quotes.

wait

Waits until `bus_name` is owned by some process on the bus. If the `--activate` is specified, that bus name will be auto-started first. It may be the same as the bus name being waited for, or different.

help

Prints help and exit.

BASH COMPLETION

`gdbus` ships with a bash completion script to complete commands, destinations, bus names, object paths and interface/method names.

EXAMPLES

This shows how to introspect an object - note that the value of each property is displayed:

```
$ gdbus introspect --system \  
    --dest org.freedesktop.NetworkManager \  
    --object-path /org/freedesktop/NetworkManager/Devices/0  
node /org/freedesktop/NetworkManager/Devices/0 {  
  interface org.freedesktop.DBus.Introspectable {  
    methods:
```

```

    Introspect(out s data);
};

interface org.freedesktop.DBus.Properties {
    methods:

    Get(in s interface,
        in s propName,
        out v value);

    Set(in s interface,
        in s propName,
        in v value);

    GetAll(in s interface,
        out a{sv} props);
};

interface org.freedesktop.NetworkManager.Device.Wired {
    signals:

    PropertiesChanged(a{sv} arg_0);

    properties:

    readonly b Carrier = false;

    readonly u Speed = 0;

    readonly s HwAddress = '00:1D:72:88:BE:97';
};

interface org.freedesktop.NetworkManager.Device {
    methods:

    Disconnect();

    signals:

    StateChanged(u arg_0,
        u arg_1,
        u arg_2);

    properties:

    readonly u DeviceType = 1;

    readonly b Managed = true;

    readwrite o Ip6Config = '/';

    readwrite o Dhcp4Config = '/';
};

```

```

readwrite o Ip4Config = '/';
readonly u State = 2;
readwrite u Ip4Address = 0;
readonly u Capabilities = 3;
readonly s Driver = 'e1000e';
readwrite s Interface = 'eth0';
readonly s Udi = '/sys/devices/pci0000:00/0000:00:19.0/net/eth0';
};
};

```

The --recurse and --only-properties options can be useful when wanting to inspect all objects owned by a particular process:

```
$ gdbus introspect --system --dest org.freedesktop.UPower --object-path / --recurse --only-properties
```

```

node / {
  node /org {
    node /org/freedesktop {
      node /org/freedesktop/UPower {
        interface org.freedesktop.UPower {
          properties:
            readonly b IsDocked = true;
            readonly b LidForceSleep = false;
            readonly b LidIsPresent = false;
            readonly b LidIsClosed = false;
            readonly b OnLowBattery = false;
            readonly b OnBattery = false;
            readonly b CanHibernate = true;
            readonly b CanSuspend = true;
            readonly s DaemonVersion = '0.9.10';
        };
        node /org/freedesktop/UPower/Policy {
        };
        node /org/freedesktop/UPower/Wakeups {
          interface org.freedesktop.UPower.Wakeups {
            properties:

```



```
--method org.freedesktop.Notifications.Notify \  
my_app_name \  
42 \  
gtk-dialog-info \  
"The Summary" \  
"Here's the body of the notification" \  
[] \  
{ } \  
5000
```

(uint32 12,)

Monitoring all objects on a service:

```
$ gdbus monitor --system --dest org.freedesktop.ConsoleKit
```

Monitoring signals from all objects owned by org.freedesktop.ConsoleKit

The name org.freedesktop.ConsoleKit is owned by :1.15

```
/org/freedesktop/ConsoleKit/Session2: org.freedesktop.ConsoleKit.Session.ActiveChanged (false,)
```

```
/org/freedesktop/ConsoleKit/Seat1: org.freedesktop.ConsoleKit.Seat.ActiveSessionChanged (",)
```

```
/org/freedesktop/ConsoleKit/Session2: org.freedesktop.ConsoleKit.Session.ActiveChanged (true,)
```

```
    /org/freedesktop/ConsoleKit/Seat1: org.freedesktop.ConsoleKit.Seat.ActiveSessionChanged
```

```
('/org/freedesktop/ConsoleKit/Session2',)
```

Monitoring a single object on a service:

```
$ gdbus monitor --system --dest org.freedesktop.NetworkManager --object-path
```

```
/org/freedesktop/NetworkManager/AccessPoint/4141
```

Monitoring signals on object /org/freedesktop/NetworkManager/AccessPoint/4141 owned by org.freedesktop.NetworkManager

The name org.freedesktop.NetworkManager is owned by :1.5

```
    /org/freedesktop/NetworkManager/AccessPoint/4141:
```

```
org.freedesktop.NetworkManager.AccessPoint.PropertiesChanged ({'Strength': <byte 0x5c>},)
```

```
    /org/freedesktop/NetworkManager/AccessPoint/4141:
```

```
org.freedesktop.NetworkManager.AccessPoint.PropertiesChanged ({'Strength': <byte 0x64>},)
```

```
    /org/freedesktop/NetworkManager/AccessPoint/4141:
```

```
org.freedesktop.NetworkManager.AccessPoint.PropertiesChanged ({'Strength': <byte 0x5e>},)
```

```
    /org/freedesktop/NetworkManager/AccessPoint/4141:
```

```
org.freedesktop.NetworkManager.AccessPoint.PropertiesChanged ({'Strength': <byte 0x64>},)
```

Emitting a signal:

```
$ gdbus emit --session --object-path /foo --signal org.bar.Foo "['foo', 'bar', 'baz']"
```

Emitting a signal to a specific process:

```
$ gdbus emit --session --object-path /bar --signal org.bar.Bar someString --dest :1.42
```

Waiting for a well-known name to be owned on the bus; this will not auto-start the service:

```
$ gdbus wait --session org.bar.SomeName
```

Auto-starting then waiting for a well-known name to be owned on the bus:

```
$ gdbus wait --session --activate org.bar.SomeName
```

Auto-starting a different service, then waiting for a well-known name to be owned on the bus. This is useful in situations where SomeName is not directly activatable:

```
$ gdbus wait --session --activate org.bar.PrerequisiteName org.bar.SomeName
```

Waiting for a well-known name and giving up after 30 seconds. By default, the timeout is disabled; or set --timeout to 0 to disable it:

```
$ gdbus wait --session --timeout 30 org.bar.SomeName
```

BUGS

Please send bug reports to either the distribution bug tracker or the upstream bug tracker at <https://gitlab.gnome.org/GNOME/glib/issues/new>.

SEE ALSO

dbus-send(1)

GIO

GDBUS(1)