



Rocky Enterprise Linux 9.2 Manual Pages on command 'sudoers.5'

C:\>man sudoers.5

SUDOERS(5) BSD File Formats Manual SUDOERS(5)

NAME

sudoers ? default sudo security policy plugin

DESCRIPTION

The sudoers policy plugin determines a user's sudo privileges. It is the default sudo policy plugin. The policy is driven by the /etc/sudoers file or, optionally in LDAP. The policy format is described in detail in the SUDOERS FILE FORMAT section.

For information on storing sudoers policy information in LDAP, please see sudoers.ldap(5).

Configuring sudo.conf for sudoers

sudo consults the sudo.conf(5) file to determine which policy and I/O logging plugins to load. If no sudo.conf(5) file is present, or if it contains no Plugin lines, sudoers will be used for policy decisions and I/O logging. To explicitly configure sudo.conf(5) to use the sudoers plugin, the following configuration can be used.

```
Plugin sudoers_policy sudoers.so
```

```
Plugin sudoers_io sudoers.so
```

Starting with sudo 1.8.5, it is possible to specify optional arguments to the sudoers plugin in the sudo.conf(5) file. These arguments, if present, should be listed after the path to the plugin (i.e., after sudoers.so). Multiple arguments may be specified, separated by white space. For example:

```
Plugin sudoers_policy sudoers.so sudoers_mode=0400
```

The following plugin arguments are supported:

`ldap_conf=pathname`

The `ldap_conf` argument can be used to override the default path to the `ldap.conf` file.

`ldap_secret=pathname`

The `ldap_secret` argument can be used to override the default path to the `ldap.secret` file.

`sudoers_file=pathname`

The `sudoers_file` argument can be used to override the default path to the `sudoers` file.

`sudoers_uid=uid`

The `sudoers_uid` argument can be used to override the default owner of the `sudoers` file. It should be specified as a numeric user-ID.

`sudoers_gid=gid`

The `sudoers_gid` argument can be used to override the default group of the `sudoers` file. It must be specified as a numeric group-ID (not a group name).

`sudoers_mode=mode`

The `sudoers_mode` argument can be used to override the default file mode for the `sudoers` file. It should be specified as an octal value.

For more information on configuring `sudo.conf(5)`, please refer to its manual.

User Authentication

The `sudoers` security policy requires that most users authenticate themselves before they can use `sudo`. A password is not required if the invoking user is `root`, if the target user is the same as the invoking user, or if the policy has disabled authentication for the user or command. Unlike `su(1)`, when `sudoers` requires authentication, it validates the invoking user's credentials, not the target user's (or `root`'s) credentials. This can be changed via the `rootpw`, `targetpw` and `runaspw` flags, described later.

If a user who is not listed in the policy tries to run a command via `sudo`, mail is sent to the proper authorities. The address used for such mail is configurable via the `mailto` Defaults entry (described later) and defaults to `root`.

Note that no mail will be sent if an unauthorized user tries to run `sudo` with the `-l` or `-v` option unless there is an authentication error and either the `mail_always` or

mail_badpass flags are enabled. This allows users to determine for themselves whether or not they are allowed to use sudo. By default, all attempts to run sudo (successful or not) are logged, regardless of whether or not mail is sent.

If sudo is run by root and the SUDO_USER environment variable is set, the sudoers policy will use this value to determine who the actual user is. This can be used by a user to log commands through sudo even when a root shell has been invoked. It also allows the -e option to remain useful even when invoked via a sudo-run script or program. Note, however, that the sudoers file lookup is still done for root, not the user specified by SUDO_USER.

sudoers uses per-user time stamp files for credential caching. Once a user has been authenticated, a record is written containing the user-ID that was used to authenticate, the terminal session ID, the start time of the session leader (or parent process) and a time stamp (using a monotonic clock if one is available). The user may then use sudo without a password for a short period of time (15 minutes unless overridden by the timestamp_timeout option). By default, sudoers uses a separate record for each terminal, which means that a user's login sessions are authenticated separately. The timestamp_type option can be used to select the type of time stamp record sudoers will use.

Logging

By default, sudoers logs both successful and unsuccessful attempts (as well as errors). The log_allowed and log_denied flags can be used to control this behavior.

Messages can be logged to syslog(3), a log file, or both. The default is to log to syslog(3) but this is configurable via the syslog and logfile settings. See LOG FORMAT for a description of the log file format.

sudoers is also capable of running a command in a pseudo-terminal and logging all input and/or output. The standard input, standard output and standard error can be logged even when not associated with a terminal. I/O logging is not on by default but can be enabled using the log_input and log_output options as well as the LOG_INPUT and LOG_OUTPUT command tags. See I/O LOG FILES for details on how I/O log files are stored.

Command environment

Since environment variables can influence program behavior, sudoers provides a means to restrict which variables from the user's environment are inherited by the command

to be run. There are two distinct ways sudoers can deal with environment variables. By default, the `env_reset` flag is enabled. This causes commands to be executed with a new, minimal environment. On AIX (and Linux systems without PAM), the environment is initialized with the contents of the `/etc/environment` file. The `HOME`, `MAIL`, `SHELL`, `LOGNAME` and `USER` environment variables are initialized based on the target user and the `SUDO_*` variables are set based on the invoking user. Additional variables, such as `DISPLAY`, `PATH` and `TERM`, are preserved from the invoking user's environment if permitted by the `env_check` or `env_keep` options. This is effectively a whitelist for environment variables. A few environment variables are treated specially. If the `PATH` and `TERM` variables are not preserved from the user's environment, they will be set to default values. The `LOGNAME` and `USER` are handled as a single entity. If one of them is preserved (or removed) from the user's environment, the other will be as well. If `LOGNAME` and `USER` are to be preserved but only one of them is present in the user's environment, the other will be set to the same value. This avoids an inconsistent environment where one of the variables describing the user name is set to the invoking user and one is set to the target user. Environment variables with a value beginning with `()` are removed unless both the name and value parts are matched by `env_keep` or `env_check`, as they may be interpreted as functions by the bash shell. Prior to version 1.8.11, such variables were always removed. If, however, the `env_reset` flag is disabled, any variables not explicitly denied by the `env_check` and `env_delete` options are inherited from the invoking process. In this case, `env_check` and `env_delete` behave like a blacklist. Prior to version 1.8.21, environment variables with a value beginning with `()` were always removed. Beginning with version 1.8.21, a pattern in `env_delete` is used to match bash shell functions instead. Since it is not possible to blacklist all potentially dangerous environment variables, use of the default `env_reset` behavior is encouraged. Environment variables specified by `env_check`, `env_delete`, or `env_keep` may include one or more `??` characters which will match zero or more characters. No other wildcard characters are supported. By default, environment variables are matched by name. However, if the pattern includes an equal sign (`?=?`), both the variables name and value must match. For example, a bash shell function could be matched as follows:

```
env_keep += "BASH_FUNC_my_func%%=(*)"
```

Without the `?=()*?` suffix, this would not match, as bash shell functions are not preserved by default.

The complete list of environment variables that are preserved or removed, as modified by global Defaults parameters in sudoers, is displayed when sudo is run by root with the `-V` option. Please note that the list of environment variables to remove varies based on the operating system sudo is running on.

Other sudoers options may influence the command environment, such as `always_set_home`, `secure_path`, `set_logname`, and `set_home`.

On systems that support PAM where the `pam_env` module is enabled for sudo, variables in the PAM environment may be merged in to the environment. If a variable in the PAM environment is already present in the user's environment, the value will only be overridden if the variable was not preserved by sudoers. When `env_reset` is enabled, variables preserved from the invoking user's environment by the `env_keep` list take precedence over those in the PAM environment. When `env_reset` is disabled, variables present in the invoking user's environment take precedence over those in the PAM environment unless they match a pattern in the `env_delete` list.

Note that the dynamic linker on most operating systems will remove variables that can control dynamic linking from the environment of set-user-ID executables, including sudo. Depending on the operating system this may include `_RLD*`, `DYLD_*`, `LD_*`, `LDR_*`, `LIBPATH`, `SHLIB_PATH`, and others. These type of variables are removed from the environment before sudo even begins execution and, as such, it is not possible for sudo to preserve them.

As a special case, if the `-i` option (initial login) is specified, sudoers will initialize the environment regardless of the value of `env_reset`. The `DISPLAY`, `PATH` and `TERM` variables remain unchanged; `HOME`, `MAIL`, `SHELL`, `USER`, and `LOGNAME` are set based on the target user. On AIX (and Linux systems without PAM), the contents of `/etc/environment` are also included. All other environment variables are removed unless permitted by `env_keep` or `env_check`, described above.

Finally, the `restricted_env_file` and `env_file` files are applied, if present. The variables in `restricted_env_file` are applied first and are subject to the same restrictions as the invoking user's environment, as detailed above. The variables in `env_file` are applied last and are not subject to these restrictions. In both cases, variables present in the files will only be set to their specified values if they

would not conflict with an existing environment variable.

SUDOERS FILE FORMAT

The sudoers file is composed of two types of entries: aliases (basically variables) and user specifications (which specify who may run what).

When multiple entries match for a user, they are applied in order. Where there are multiple matches, the last match is used (which is not necessarily the most specific match).

The sudoers file grammar will be described below in Extended Backus-Naur Form (EBNF).

Don't despair if you are unfamiliar with EBNF; it is fairly simple, and the definitions below are annotated.

Quick guide to EBNF

EBNF is a concise and exact way of describing the grammar of a language. Each EBNF definition is made up of production rules. E.g.,
symbol ::= definition | alternate1 | alternate2 ...

Each production rule references others and thus makes up a grammar for the language.

EBNF also contains the following operators, which many readers will recognize from regular expressions. Do not, however, confuse them with ?wildcard? characters, which have different meanings.

? Means that the preceding symbol (or group of symbols) is optional. That is, it may appear once or not at all.

* Means that the preceding symbol (or group of symbols) may appear zero or more times.

+ Means that the preceding symbol (or group of symbols) may appear one or more times.

Parentheses may be used to group symbols together. For clarity, we will use single quotes (") to designate what is a verbatim character string (as opposed to a symbol name).

Aliases

There are four kinds of aliases: User_Alias, Runas_Alias, Host_Alias and Cmnd_Alias.

```
Alias ::= 'User_Alias' User_Alias_Spec (':' User_Alias_Spec)* |  
        'Runas_Alias' Runas_Alias_Spec (':' Runas_Alias_Spec)* |  
        'Host_Alias' Host_Alias_Spec (':' Host_Alias_Spec)* |  
        'Cmnd_Alias' Cmnd_Alias_Spec (':' Cmnd_Alias_Spec)*
```

User_Alias ::= NAME

User_Alias_Spec ::= User_Alias '=' User_List

Runas_Alias ::= NAME

Runas_Alias_Spec ::= Runas_Alias '=' Runas_List

Host_Alias ::= NAME

Host_Alias_Spec ::= Host_Alias '=' Host_List

Cmnd_Alias ::= NAME

Cmnd_Alias_Spec ::= Cmnd_Alias '=' Cmnd_List

NAME ::= [A-Z]([A-Z][0-9_]*)

Each alias definition is of the form

Alias_Type NAME = item1, item2, ...

where Alias_Type is one of User_Alias, Runas_Alias, Host_Alias, or Cmnd_Alias. A

NAME is a string of uppercase letters, numbers, and underscore characters (?_?). A

NAME must start with an uppercase letter. It is possible to put several alias defini?

initions of the same type on a single line, joined by a colon (?:?). E.g.,

Alias_Type NAME = item1, item2, item3 : NAME = item4, item5

It is a syntax error to redefine an existing alias. It is possible to use the same

name for aliases of different types, but this is not recommended.

The definitions of what constitutes a valid alias member follow.

User_List ::= User |

User ',' User_List

User ::= '!*' user name |

'!* #uid |

'!* %group |

'!* %#gid |

'!* +netgroup |

'!* %:nonunix_group |

'!* %:#nonunix_gid |

'!* User_Alias

A User_List is made up of one or more user names, user-IDs (prefixed with ?#?), sys?

tem group names and IDs (prefixed with ?%? and ?%#? respectively), netgroups (pre?

fixed with ?+?), non-Unix group names and IDs (prefixed with ?%:? and ?%:#? respec?

tively) and User_Aliases. Each list item may be prefixed with zero or more !? opera?

tors. An odd number of !? operators negate the value of the item; an even number just cancel each other out. User netgroups are matched using the user and domain members only; the host member is not used when matching.

A user name, uid, group, gid, netgroup, nonunix_group or nonunix_gid may be enclosed in double quotes to avoid the need for escaping special characters. Alternately, special characters may be specified in escaped hex mode, e.g., \x20 for space. When using double quotes, any prefix characters must be included inside the quotes.

The actual nonunix_group and nonunix_gid syntax depends on the underlying group provider plugin. For instance, the QAS AD plugin supports the following formats:

- ? Group in the same domain: "%:Group Name"
- ? Group in any domain: "%:Group Name@FULLY.QUALIFIED.DOMAIN"
- ? Group SID: "%:S-1-2-34-5678901234-5678901234-5678901234-567"

See GROUP PROVIDER PLUGINS for more information.

Note that quotes around group names are optional. Unquoted strings must use a backslash (\) to escape spaces and special characters. See Other special characters and reserved words for a list of characters that need to be escaped.

```
Runas_List ::= Runas_Member |
             Runas_Member ',' Runas_List
Runas_Member ::= '!*' user name |
                '!*' #uid |
                '!*' %group |
                '!*' %#gid |
                '!*' %:nonunix_group |
                '!*' %:#nonunix_gid |
                '!*' +netgroup |
                '!*' Runas_Alias
```

A Runas_List is similar to a User_List except that instead of User_Aliases it can contain Runas_Aliases. Note that user names and groups are matched as strings. In other words, two users (groups) with the same user (group) ID are considered to be distinct. If you wish to match all user names with the same user-ID (e.g., root and toor), you can use a user-ID instead of a name (#0 in the example given). Note that the user-ID or group-ID specified in a Runas_Member need not be listed in the password or group database.

```
Host_List ::= Host |  
            Host ',' Host_List
```

```
Host ::= '!*' host name |  
        '!*' ip_addr |  
        '!*' network(/netmask)? |  
        '!*' +netgroup |  
        '!*' Host_Alias
```

A Host_List is made up of one or more host names, IP addresses, network numbers, netgroups (prefixed with ?+?) and other aliases. Again, the value of an item may be negated with the !? operator. Host netgroups are matched using the host (both qualified and unqualified) and domain members only; the user member is not used when matching. If you specify a network number without a netmask, sudo will query each of the local host's network interfaces and, if the network number corresponds to one of the host's network interfaces, will use the netmask of that interface. The netmask may be specified either in standard IP address notation (e.g., 255.255.255.0 or ffff:ffff:ffff:ffff:), or CIDR notation (number of bits, e.g., 24 or 64). A host name may include shell-style wildcards (see the Wildcards section below), but unless the host name command on your machine returns the fully qualified host name, you'll need to use the fqdn flag for wildcards to be useful. Note that sudo only inspects actual network interfaces; this means that IP address 127.0.0.1 (localhost) will never match. Also, the host name ?localhost? will only match if that is the actual host name, which is usually only the case for non-networked systems.

```
digest ::= [A-Fa-f0-9]+ |  
           [A-Za-z0-9\+/=]+
```

```
Digest_Spec ::= "sha224" ':' digest |  
               "sha256" ':' digest |  
               "sha384" ':' digest |  
               "sha512" ':' digest
```

```
Cmnd_List ::= Cmnd |  
            Cmnd ',' Cmnd_List
```

```
command name ::= file name |  
               file name args |  
               file name ""
```

```
Cmnd ::= Digest_Spec? '!* command name |
      '!* directory |
      '!* "sudoedit" |
      '!* Cmnd_Alias
```

A Cmnd_List is a list of one or more command names, directories, and other aliases.

A command name is a fully qualified file name which may include shell-style wildcards (see the Wildcards section below). A simple file name allows the user to run the command with any arguments they wish. However, you may also specify command line arguments (including wildcards). Alternately, you can specify "" to indicate that the command may only be run without command line arguments. A directory is a fully qualified path name ending in a /?. When you specify a directory in a Cmnd_List, the user will be able to run any file within that directory (but not in any sub-directories therein).

If a Cmnd has associated command line arguments, then the arguments in the Cmnd must match exactly those given by the user on the command line (or match the wildcards if there are any). Note that the following characters must be escaped with a \? if they are used in command arguments: ?,?, ?:?, ?=?, ?\?. The built-in command ?sudoedit? is used to permit a user to run sudo with the -e option (or as sudoedit). It may take command line arguments just as a normal command does. Note that ?sudoedit? is a command built into sudo itself and must be specified in the sudoers file without a leading path. If a leading path is present, for example /usr/bin/sudoedit, the path name will be silently converted to ?sudoedit?. A fully-qualified path for sudoedit is treated as an error by visudo.

If a command name is prefixed with a Digest_Spec, the command will only match successfully if it can be verified using the specified SHA-2 digest. The following digest formats are supported: sha224, sha256, sha384 and sha512. The string may be specified in either hex or base64 format (base64 is more compact). There are several utilities capable of generating SHA-2 digests in hex format such as openssl, shasum, sha224sum, sha256sum, sha384sum, sha512sum.

For example, using openssl:

```
$ openssl dgst -sha224 /bin/l
```

```
SHA224(/bin/l)= 118187da8364d490b4a7debbf483004e8f3e053ec954309de2c41a25
```

It is also possible to use openssl to generate base64 output:

```
$ openssl dgst -binary -sha224 /bin/ls | openssl base64
```

```
EYGH2oNk1JC0p9679IMATo8+BT7JVDCd4sQaJQ==
```

Warning, if the user has write access to the command itself (directly or via a sudo command), it may be possible for the user to replace the command after the digest check has been performed but before the command is executed. A similar race condition exists on systems that lack the `fexecve(2)` system call when the directory in which the command is located is writable by the user. See the description of the `fdexec` setting for more information on how sudo executes commands that have an associated digest.

Command digests are only supported by version 1.8.7 or higher.

Defaults

Certain configuration options may be changed from their default values at run-time via one or more `Default_Entry` lines. These may affect all users on any host, all users on a specific host, a specific user, a specific command, or commands being run as a specific user. Note that per-command entries may not include command line arguments. If you need to specify arguments, define a `Cmnd_Alias` and reference that instead.

```
Default_Type ::= 'Defaults' |
```

```
    'Defaults' '@' Host_List |
```

```
    'Defaults' ':' User_List |
```

```
    'Defaults' '!' Cmnd_List |
```

```
    'Defaults' '>' Runas_List
```

```
Default_Entry ::= Default_Type Parameter_List
```

```
Parameter_List ::= Parameter |
```

```
    Parameter ',' Parameter_List
```

```
Parameter ::= Parameter '=' Value |
```

```
    Parameter '+=' Value |
```

```
    Parameter '-=' Value |
```

```
    '!*' Parameter
```

Parameters may be flags, integer values, strings, or lists. Flags are implicitly boolean and can be turned off via the `?!?` operator. Some integer, string and list parameters may also be used in a boolean context to disable them. Values may be enclosed in double quotes (") when they contain multiple words. Special characters

may be escaped with a backslash (?\\?).

Lists have two additional assignment operators, += and -=. These operators are used to add to and delete from a list respectively. It is not an error to use the -= operator to remove an element that does not exist in a list.

Defaults entries are parsed in the following order: generic, host, user and runas Defaults first, then command defaults. If there are multiple Defaults settings of the same type, the last matching setting is used. The following Defaults settings are parsed before all others since they may affect subsequent entries: fqdn, group_plugin, runas_default, sudoers_locale.

See SUDOERS OPTIONS for a list of supported Defaults parameters.

User specification

```
User_Spec ::= User_List Host_List '=' Cmnd_Spec_List \
           (':' Host_List '=' Cmnd_Spec_List)*
Cmnd_Spec_List ::= Cmnd_Spec |
                  Cmnd_Spec ',' Cmnd_Spec_List
Cmnd_Spec ::= Runas_Spec? Option_Spec* Tag_Spec* Cmnd
Runas_Spec ::= '(' Runas_List? (':' Runas_List)? ')'
Option_Spec ::= (SELinux_Spec | Date_Spec | Timeout_Spec)
SELinux_Spec ::= ('ROLE=role' | 'TYPE=type')
Date_Spec ::= ('NOTBEFORE=timestamp' | 'NOTAFTER=timestamp')
Timeout_Spec ::= 'TIMEOUT=timeout'
Tag_Spec ::= ('EXEC:' | 'NOEXEC:' | 'FOLLOW:' | 'NOFOLLOW' |
             'LOG_INPUT:' | 'NOLOG_INPUT:' | 'LOG_OUTPUT:' |
             'NOLOG_OUTPUT:' | 'MAIL:' | 'NOMAIL:' | 'PASSWD:' |
             'NOPASSWD:' | 'SETENV:' | 'NOSETENV:')
```

A user specification determines which commands a user may run (and as what user) on specified hosts. By default, commands are run as root, but this can be changed on a per-command basis.

The basic structure of a user specification is ?who where = (as_whom) what?. Let's break that down into its constituent parts:

Runas_Spec

A Runas_Spec determines the user and/or the group that a command may be run as. A fully-specified Runas_Spec consists of two Runas_Lists (as defined above) separated

by a colon (?:) and enclosed in a set of parentheses. The first Runas_List indicates which users the command may be run as via the -u option. The second defines a list of groups that can be specified via the -g option in addition to any of the target user's groups. If both Runas_Lists are specified, the command may be run with any combination of users and groups listed in their respective Runas_Lists. If only the first is specified, the command may be run as any user in the list but no group option may be specified. If the first Runas_List is empty but the second is specified, the command may be run as the invoking user with the group set to any listed in the Runas_List. If both Runas_Lists are empty, the command may only be run as the invoking user. If no Runas_Spec is specified the command may be run as root and no group may be specified.

A Runas_Spec sets the default for the commands that follow it. What this means is that for the entry:

```
dgb boulder = (operator) /bin/lis, /bin/kill, /usr/bin/lprm
```

The user dgb may run /bin/lis, /bin/kill, and /usr/bin/lprm on the host boulder but only as operator. E.g.,

```
$ sudo -u operator /bin/lis
```

It is also possible to override a Runas_Spec later on in an entry. If we modify the entry like so:

```
dgb boulder = (operator) /bin/lis, (root) /bin/kill, /usr/bin/lprm
```

Then user dgb is now allowed to run /bin/lis as operator, but /bin/kill and /usr/bin/lprm as root.

We can extend this to allow dgb to run /bin/lis with either the user or group set to operator:

```
dgb boulder = (operator : operator) /bin/lis, (root) /bin/kill, \
    /usr/bin/lprm
```

Note that while the group portion of the Runas_Spec permits the user to run as command with that group, it does not force the user to do so. If no group is specified on the command line, the command will run with the group listed in the target user's password database entry. The following would all be permitted by the sudoers entry above:

```
$ sudo -u operator /bin/lis
```

```
$ sudo -u operator -g operator /bin/lis
```

```
$ sudo -g operator /bin/ls
```

In the following example, user tcm may run commands that access a modem device file with the dialer group.

```
tcm boulder = (:dialer) /usr/bin/tip, /usr/bin/cu,\n    /usr/local/bin/minicom
```

Note that in this example only the group will be set, the command still runs as user tcm. E.g.

```
$ sudo -g dialer /usr/bin/cu
```

Multiple users and groups may be present in a Runas_Spec, in which case the user may select any combination of users and groups via the -u and -g options. In this exam?

ple:

```
alan ALL = (root, bin : operator, system) ALL
```

user alan may run any command as either user root or bin, optionally setting the group to operator or system.

Option_Spec

A Cmnd may have zero or more options associated with it. Options may consist of SELinux roles and/or types, start and/or end dates and command timeouts. Once an option is set for a Cmnd, subsequent Cmnds in the Cmnd_Spec_List, inherit that option unless it is overridden by another option.

SELinux_Spec

On systems with SELinux support, sudoers file entries may optionally have an SELinux role and/or type associated with a command. If a role or type is specified with the command it will override any default values specified in sudoers. A role or type specified on the command line, however, will supersede the values in sudoers.

Date_Spec

sudoers rules can be specified with a start and end date via the NOTBEFORE and NOTAFTER settings. The time stamp must be specified in Generalized Time as defined by RFC 4517. The format is effectively `yyymmddHHMMSSZ` where the minutes and seconds are optional. The `?Z?` suffix indicates that the time stamp is in Coordinated Universal Time (UTC). It is also possible to specify a timezone offset from UTC in hours and minutes instead of a `?Z?`. For example, `?-0500?` would correspond to Eastern Standard time in the US. As an extension, if no `?Z?` or timezone offset is specified, local time will be used.

The following are all valid time stamps:

20170214083000Z

2017021408Z

20160315220000-0500

20151201235900

Timeout_Spec

A command may have a timeout associated with it. If the timeout expires before the command has exited, the command will be terminated. The timeout may be specified in combinations of days, hours, minutes and seconds with a single-letter case-insensitive suffix that indicates the unit of time. For example, a timeout of 7 days, 8 hours, 30 minutes and 10 seconds would be written as 7d8h30m10s. If a number is specified without a unit, seconds are assumed. Any of the days, minutes, hours or seconds may be omitted. The order must be from largest to smallest unit and a unit may not be specified more than once.

The following are all valid timeout values: 7d8h30m10s, 14d, 8h30m, 600s, 3600. The following are invalid timeout values: 12m2w1d, 30s10m4h, 1d2d3h.

This setting is only supported by version 1.8.20 or higher.

Tag_Spec

A command may have zero or more tags associated with it. The following tag values are supported: EXEC, NOEXEC, FOLLOW, NOFOLLOW, LOG_INPUT, NOLOG_INPUT, LOG_OUTPUT, NOLOG_OUTPUT, MAIL, NOMAIL, PASSWD, NOPASSWD, SETENV, and NOSETENV. Once a tag is set on a Cmnd, subsequent Cmnds in the Cmnd_Spec_List, inherit the tag unless it is overridden by the opposite tag (in other words, PASSWD overrides NOPASSWD and NOEXEC overrides EXEC).

EXEC and NOEXEC

If sudo has been compiled with noexec support and the underlying operating system supports it, the NOEXEC tag can be used to prevent a dynamically-linked executable from running further commands itself.

In the following example, user aaron may run /usr/bin/more and /usr/bin/vi but shell escapes will be disabled.

```
aaron shanty = NOEXEC: /usr/bin/more, /usr/bin/vi
```

See the Preventing shell escapes section below for more details on how NOEXEC works and whether or not it will work on your system.

FOLLOW and NOFOLLOW Starting with version 1.8.15, sudoedit will not open a file that is a symbolic link unless the sudoedit_follow flag is enabled. The FOLLOW and NOFOLLOW tags override the value of sudoedit_follow and can be used to permit (or deny) the editing of symbolic links on a per-command basis. These tags are only effective for the sudoedit command and are ignored for all other commands.

LOG_INPUT and NOLOG_INPUT

These tags override the value of the log_input flag on a per-command basis. For more information, see the description of log_input in the SUDOERS OPTIONS section below.

LOG_OUTPUT and NOLOG_OUTPUT

These tags override the value of the log_output flag on a per-command basis. For more information, see the description of log_output in the SUDOERS OPTIONS section below.

MAIL and NOMAIL

These tags provide fine-grained control over whether mail will be sent when a user runs a command by overriding the value of the mail_all_cmnds flag on a per-command basis. They have no effect when sudo is run with the -l or -v options. A NOMAIL tag will also override the mail_always and mail_no_perms options. For more information, see the descriptions of mail_all_cmnds, mail_always, and mail_no_perms in the SUDOERS OPTIONS section below.

PASSWD and NOPASSWD

By default, sudo requires that a user authenticate him or herself before running a command. This behavior can be modified via the NOPASSWD tag. Like a Runas_Spec, the NOPASSWD tag sets a default for the commands that follow it in the Cmnd_Spec_List. Conversely, the PASSWD tag can be used to reverse things. For example:

```
ray    rushmore = NOPASSWD: /bin/kill, /bin/lS, /usr/bin/lprm
```

would allow the user ray to run /bin/kill, /bin/lS, and /usr/bin/lprm as root on the machine rushmore without authenticating himself. If we only want ray to be able to run /bin/kill without a password the entry would be:

```
ray    rushmore = NOPASSWD: /bin/kill, PASSWD: /bin/lS, /usr/bin/lprm
```

Note, however, that the PASSWD tag has no effect on users who are in the group specified by the exempt_group setting.

By default, if the NOPASSWD tag is applied to any of a user's entries for the current host, the user will be able to run `sudo -l` without a password. Additionally, a user may only run `sudo -v` without a password if all of the user's entries for the current host have the NOPASSWD tag. This behavior may be overridden via the `verifypw` and `listpw` options.

SETENV and NOSETENV

These tags override the value of the `setenv` flag on a per-command basis. Note that if SETENV has been set for a command, the user may disable the `env_reset` flag from the command line via the `-E` option. Additionally, environment variables set on the command line are not subject to the restrictions imposed by `env_check`, `env_delete`, or `env_keep`. As such, only trusted users should be allowed to set variables in this manner. If the command matched is ALL, the SETENV tag is implied for that command; this default may be overridden by use of the NOSETENV tag.

Wildcards

sudo allows shell-style wildcards (aka meta or glob characters) to be used in host names, path names and command line arguments in the sudoers file. Wildcard matching is done via the `glob(3)` and `fnmatch(3)` functions as specified by IEEE Std 1003.1 (?POSIX.1?).

* Matches any set of zero or more characters (including white space).

? Matches any single character (including white space).

[...] Matches any character in the specified range.

[!...] Matches any character not in the specified range.

\x For any character `?x?`, evaluates to `?x?`. This is used to escape special characters such as: `?*?`, `???`, `?[?`, and `?]??`.

Note that these are not regular expressions. Unlike a regular expression there is no way to match one or more characters within a range.

Character classes may be used if your system's `glob(3)` and `fnmatch(3)` functions support them. However, because the `?:?` character has special meaning in sudoers, it must be escaped. For example:

```
/bin/l[s [[\:alpha\:]]*
```

Would match any file name beginning with a letter.

Note that a forward slash (`/?`) will not be matched by wildcards used in the file name portion of the command. This is to make a path like:

```
/usr/bin/*
```

match `/usr/bin/who` but not `/usr/bin/X11/xterm`.

When matching the command line arguments, however, a slash does get matched by wild?

cards since command line arguments may contain arbitrary strings and not just path names.

Wildcards in command line arguments should be used with care.

Command line arguments are matched as a single, concatenated string. This mean a wildcard character such as `???` or `?*?` will match across word boundaries, which may be unexpected. For example, while a sudoers entry like:

```
%operator ALL = /bin/cat /var/log/messages*
```

will allow command like:

```
$ sudo cat /var/log/messages.1
```

It will also allow:

```
$ sudo cat /var/log/messages /etc/shadow
```

which is probably not what was intended. In most cases it is better to do command line processing outside of the sudoers file in a scripting language.

Exceptions to wildcard rules

The following exceptions apply to the above rules:

"" If the empty string "" is the only command line argument in the sudoers file entry it means that command is not allowed to be run with any arguments.

sudoedit Command line arguments to the sudoedit built-in command should always be path names, so a forward slash (/?/) will not be matched by a wildcard.

Including other files from within sudoers

It is possible to include other sudoers files from within the sudoers file currently being parsed using the `#include` and `#includedir` directives.

This can be used, for example, to keep a site-wide sudoers file in addition to a local, per-machine file. For the sake of this example the site-wide sudoers file will be `/etc/sudoers` and the per-machine one will be `/etc/sudoers.local`. To include `/etc/sudoers.local` from within `/etc/sudoers` we would use the following line in `/etc/sudoers`:

```
#include /etc/sudoers.local
```

When sudo reaches this line it will suspend processing of the current file

(/etc/sudoers) and switch to /etc/sudoers.local. Upon reaching the end of /etc/sudoers.local, the rest of /etc/sudoers will be processed. Files that are included may themselves include other files. A hard limit of 128 nested include files is enforced to prevent include file loops.

If the path to the include file is not fully-qualified (does not begin with a /), it must be located in the same directory as the sudoers file it was included from.

For example, if /etc/sudoers contains the line:

```
#include sudoers.local
```

the file that will be included is /etc/sudoers.local.

The file name may also include the %h escape, signifying the short form of the host name. In other words, if the machine's host name is xerxes, then

```
#include /etc/sudoers.%h
```

will cause sudo to include the file /etc/sudoers.xerxes.

The #includedir directive can be used to create a sudoers.d directory that the system package manager can drop sudoers file rules into as part of package installation.

For example, given:

```
#includedir /etc/sudoers.d
```

sudo will suspend processing of the current file and read each file in /etc/sudoers.d, skipping file names that end in ~ or contain a ? character to avoid causing problems with package manager or editor temporary/backup files. Files are parsed in sorted lexical order. That is, /etc/sudoers.d/01_first will be parsed before /etc/sudoers.d/10_second. Be aware that because the sorting is lexical, not numeric, /etc/sudoers.d/1_whoops would be loaded after /etc/sudoers.d/10_second. Using a consistent number of leading zeroes in the file names can be used to avoid such problems. After parsing the files in the directory, control returns to the file that contained the #includedir directive.

Note that unlike files included via #include, visudo will not edit the files in a #includedir directory unless one of them contains a syntax error. It is still possible to run visudo with the -f flag to edit the files directly, but this will not catch the redefinition of an alias that is also present in a different file.

Other special characters and reserved words

The pound sign (#) is used to indicate a comment (unless it is part of a #include directive or unless it occurs in the context of a user name and is followed by one or

more digits, in which case it is treated as a user-ID). Both the comment character and any text after it, up to the end of the line, are ignored.

The reserved word ALL is a built-in alias that always causes a match to succeed. It can be used wherever one might otherwise use a Cmnd_Alias, User_Alias, Runas_Alias, or Host_Alias. You should not try to define your own alias called ALL as the built-in alias will be used in preference to your own. Please note that using ALL can be dangerous since in a command context, it allows the user to run any command on the system.

An exclamation point (!) can be used as a logical not operator in a list or alias as well as in front of a Cmnd. This allows one to exclude certain values. For the ! operator to be effective, there must be something for it to exclude. For example, to match all users except for root one would use:

```
ALL,!root
```

If the ALL is omitted, as in:

```
!root
```

it would explicitly deny root but not match any other users. This is different from a true negation operator.

Note, however, that using a ! in conjunction with the built-in ALL alias to allow a user to run all but a few commands rarely works as intended (see SECURITY NOTES below).

Long lines can be continued with a backslash (\) as the last character on the line.

White space between elements in a list as well as special syntactic characters in a User Specification (=?, !:, !(, !?)) is optional.

The following characters must be escaped with a backslash (\) when used as part of a word (e.g., a user name or host name): !, =, :, ,(,)?, \.

SUDOERS OPTIONS

sudo's behavior can be modified by Default_Entry lines, as explained earlier. A list of all supported Defaults parameters, grouped by type, are listed below.

Boolean Flags:

```
always_query_group_plugin
```

If a group_plugin is configured, use it to resolve groups of the form %group as long as there is not also a system group of the same name. Normally, only groups of the form %:group are passed to the

group_plugin. This flag is off by default.

always_set_home If enabled, sudo will set the HOME environment variable to the home directory of the target user (which is the root user unless the -u option is used). This flag is largely obsolete and has no effect unless the env_reset flag has been disabled or HOME is present in the env_keep list, both of which are strongly discouraged. This flag is off by default.

authenticate If set, users must authenticate themselves via a password (or other means of authentication) before they may run commands. This default may be overridden via the PASSWD and NOPASSWD tags. This flag is on by default.

case_insensitive_group

If enabled, group names in sudoers will be matched in a case insensitive manner. This may be necessary when users are stored in LDAP or AD. This flag is on by default.

case_insensitive_user

If enabled, user names in sudoers will be matched in a case insensitive manner. This may be necessary when groups are stored in LDAP or AD. This flag is on by default.

closefrom_override

If set, the user may use the -C option which overrides the default starting point at which sudo begins closing open file descriptors. This flag is off by default.

compress_io If set, and sudo is configured to log a command's input or output, the I/O logs will be compressed using zlib. This flag is on by default when sudo is compiled with zlib support.

exec_background By default, sudo runs a command as the foreground process as long as sudo itself is running in the foreground. When the exec_background flag is enabled and the command is being run in a pseudo-terminal (due to I/O logging or the use_pty flag), the command will be run as a background process. Attempts to read from the controlling terminal (or to change terminal settings) will result in the command being suspended with the SIGTTIN signal (or

SIGTTOU in the case of terminal settings). If this happens when sudo is a foreground process, the command will be granted the control of the terminal and resumed in the foreground with no user intervention required. The advantage of initially running the command in the background is that sudo need not read from the terminal unless the command explicitly requests it. Otherwise, any terminal input must be passed to the command, whether it has required it or not (the kernel buffers terminals so it is not possible to tell whether the command really wants the input). This is different from historic sudo behavior or when the command is not being run in a pseudo-terminal.

For this to work seamlessly, the operating system must support the automatic restarting of system calls. Unfortunately, not all operating systems do this by default, and even those that do may have bugs. For example, macOS fails to restart the tcgetattr() and tcsetattr() system calls (this is a bug in macOS). Furthermore, because this behavior depends on the command stopping with the SIGTTIN or SIGTTOU signals, programs that catch these signals and suspend themselves with a different signal (usually SIGTOP) will not be automatically foregrounded. Some versions of the linux su(1) command behave this way. This flag is off by default.

This setting is only supported by version 1.8.7 or higher. It has no effect unless I/O logging is enabled or the use_pty flag is enabled.

`env_editor` If set, visudo will use the value of the SUDO_EDITOR, VISUAL or EDITOR environment variables before falling back on the default editor list. Note that visudo is typically run as root so this flag may allow a user with visudo privileges to run arbitrary commands as root without logging. An alternative is to place a colon-separated list of "safe" editors into the editor variable. visudo will then only use SUDO_EDITOR, VISUAL or EDITOR if they match a value specified in editor. If the env_reset flag is enabled, the SUDO_EDITOR, VISUAL and/or EDITOR environment variables must be

present in the `env_keep` list for the `env_editor` flag to function when `visudo` is invoked via `sudo`. This flag is on by default.

`env_reset` If set, `sudo` will run the command in a minimal environment containing the `TERM`, `PATH`, `HOME`, `MAIL`, `SHELL`, `LOGNAME`, `USER` and `SUDO_*` variables. Any variables in the caller's environment or in the file specified by the `restricted_env_file` setting that match the `env_keep` and `env_check` lists are then added, followed by any variables present in the file specified by the `env_file` setting (if any). The contents of the `env_keep` and `env_check` lists, as modified by global Defaults parameters in `sudoers`, are displayed when `sudo` is run by root with the `-V` option. If the `secure_path` setting is enabled, its value will be used for the `PATH` environment variable. This flag is on by default.

`fast_glob` Normally, `sudo` uses the `glob(3)` function to do shell-style globbing when matching path names. However, since it accesses the filesystem, `glob(3)` can take a long time to complete for some patterns, especially when the pattern references a network file system that is mounted on demand (auto mounted). The `fast_glob` flag causes `sudo` to use the `fnmatch(3)` function, which does not access the filesystem to do its matching. The disadvantage of `fast_glob` is that it is unable to match relative path names such as `./ls` or `../bin/ls`. This has security implications when path names that include globbing characters are used with the negation operator, `!?`, as such rules can be trivially bypassed. As such, this flag should not be used when the `sudoers` file contains rules that contain negated path names which include globbing characters. This flag is off by default.

`fqdn` Set this flag if you want to put fully qualified host names in the `sudoers` file when the local host name (as returned by the `hostname` command) does not contain the domain name. In other words, instead of `myhost` you would use `myhost.mydomain.edu`. You may still use the short form if you wish (and even mix the two). This flag is only effective when the `?canonical?` host name, as returned by the

getaddrinfo() or gethostbyname() function, is a fully-qualified domain name. This is usually the case when the system is configured to use DNS for host name resolution.

If the system is configured to use the /etc/hosts file in preference to DNS, the canonical host name may not be fully-qualified. The order that sources are queried for host name resolution is usually specified in the /etc/nsswitch.conf, /etc/netsvc.conf, /etc/host.conf, or, in some cases, /etc/resolv.conf file. In the /etc/hosts file, the first host name of the entry is considered to be the canonical name; subsequent names are aliases that are not used by sudoers. For example, the following hosts file line for the machine xyzzy has the fully-qualified domain name as the canonical host name, and the short version as an alias.

```
192.168.1.1 xyzzy.sudo.ws xyzzy
```

If the machine's hosts file entry is not formatted properly, the fqdn flag will not be effective if it is queried before DNS.

Beware that when using DNS for host name resolution, turning on fqdn requires sudoers to make DNS lookups which renders sudo unusable if DNS stops working (for example if the machine is disconnected from the network). Also note that just like with the hosts file, you must use the canonical name as DNS knows it. That is, you may not use a host alias (CNAME entry) due to performance issues and the fact that there is no way to get all aliases from DNS.

This flag is on by default.

ignore_audit_errors

Allow commands to be run even if sudoers cannot write to the audit log. If enabled, an audit log write failure is not treated as a fatal error. If disabled, a command may only be run after the audit event is successfully written. This flag is only effective on systems for which sudoers supports audit logging, including FreeBSD, Linux, macOS and Solaris. This flag is on by default.

ignore_dot If set, sudo will ignore "." or "" (both denoting current directory) in the PATH environment variable; the PATH itself is not modified.

ified. This flag is off by default.

ignore_iolog_errors

Allow commands to be run even if sudoers cannot write to the I/O log. If enabled, an I/O log write failure is not treated as a fatal error. If disabled, the command will be terminated if the I/O log cannot be written to. This flag is off by default.

ignore_logfile_errors

Allow commands to be run even if sudoers cannot write to the log file. If enabled, a log file write failure is not treated as a fatal error. If disabled, a command may only be run after the log file entry is successfully written. This flag only has an effect when sudoers is configured to use file-based logging via the logfile setting. This flag is on by default.

ignore_local_sudoers

If set via LDAP, parsing of /etc/sudoers will be skipped. This is intended for Enterprises that wish to prevent the usage of local sudoers files so that only LDAP is used. This thwarts the efforts of rogue operators who would attempt to add roles to /etc/sudoers. When this flag is enabled, /etc/sudoers does not even need to exist. Since this flag tells sudo how to behave when no specific LDAP entries have been matched, this sudoOption is only meaningful for the cn=defaults section. This flag is off by default.

ignore_unknown_defaults

If set, sudo will not produce a warning if it encounters an unknown Defaults entry in the sudoers file or an unknown sudoOption in LDAP. This flag is off by default.

insults If set, sudo will insult users when they enter an incorrect password. This flag is off by default.

log_allowed If set, sudoers will log commands allowed by the policy to the system audit log (where supported) as well as to syslog and/or a log file. This flag is on by default.

This setting is only supported by version 1.8.29 or higher.

log_denied If set, sudoers will log commands denied by the policy to the sys?

tem audit log (where supported) as well as to syslog and/or a log file. This flag is on by default.

This setting is only supported by version 1.8.29 or higher.

log_host If set, the host name will be included in log entries written to the file configured by the logfile setting. This flag is off by default.

log_input If set, sudo will run the command in a pseudo-terminal and log all user input. If the standard input is not connected to the user's tty, due to I/O redirection or because the command is part of a pipeline, that input is also captured and stored in a separate log file. Anything sent to the standard input will be consumed, regardless of whether or not the command run via sudo is actually reading the standard input. This may have unexpected results when using sudo in a shell script that expects to process the standard input. For more information about I/O logging, see the I/O LOG FILES section. This flag is off by default.

log_output If set, sudo will run the command in a pseudo-terminal and log all output that is sent to the screen, similar to the script(1) command. For more information about I/O logging, see the I/O LOG FILES section. This flag is off by default.

log_year If set, the four-digit year will be logged in the (non-syslog) sudo log file. This flag is off by default.

long_otp_prompt When validating with a One Time Password (OTP) scheme such as S/Key or OPIE, a two-line prompt is used to make it easier to cut and paste the challenge to a local window. It's not as pretty as the default but some people find it more convenient. This flag is off by default.

mail_all_cmnds Send mail to the mailto user every time a user attempts to run a command via sudo (this includes sudoedit). No mail will be sent if the user runs sudo with the -l or -v option unless there is an authentication error and the mail_badpass flag is also set. This flag is off by default.

mail_always Send mail to the mailto user every time a user runs sudo. This

flag is off by default.

`mail_badpass` Send mail to the `mailto` user if the user running `sudo` does not enter the correct password. If the command the user is attempting to run is not permitted by `sudoers` and one of the `mail_all_cmds`, `mail_always`, `mail_no_host`, `mail_no_perms` or `mail_no_user` flags are set, this flag will have no effect. This flag is off by default.

`mail_no_host` If set, mail will be sent to the `mailto` user if the invoking user exists in the `sudoers` file, but is not allowed to run commands on the current host. This flag is off by default.

`mail_no_perms` If set, mail will be sent to the `mailto` user if the invoking user is allowed to use `sudo` but the command they are trying is not listed in their `sudoers` file entry or is explicitly denied. This flag is off by default.

`mail_no_user` If set, mail will be sent to the `mailto` user if the invoking user is not in the `sudoers` file. This flag is on by default.

`match_group_by_gid`

By default, `sudoers` will look up each group the user is a member of by group-ID to determine the group name (this is only done once). The resulting list of the user's group names is used when matching groups listed in the `sudoers` file. This works well on systems where the number of groups listed in the `sudoers` file is larger than the number of groups a typical user belongs to. On systems where group lookups are slow, where users may belong to a large number of groups, and where the number of groups listed in the `sudoers` file is relatively small, it may be prohibitively expensive and running commands via `sudo` may take longer than normal. On such systems it may be faster to use the `match_group_by_gid` flag to avoid resolving the user's group-IDs to group names. In this case, `sudoers` must look up any group name listed in the `sudoers` file and use the group-ID instead of the group name when determining whether the user is a member of the group.

Note that if `match_group_by_gid` is enabled, group database lookups performed by `sudoers` will be keyed by group name as opposed to

group-ID. On systems where there are multiple sources for the group database, it is possible to have conflicting group names or group-IDs in the local `/etc/group` file and the remote group data base. On such systems, enabling or disabling `match_group_by_gid` can be used to choose whether group database queries are performed by name (enabled) or ID (disabled), which may aid in working around group entry conflicts.

The `match_group_by_gid` flag has no effect when sudoers data is stored in LDAP. This flag is off by default.

This setting is only supported by version 1.8.18 or higher.

`netgroup_tuple` If set, netgroup lookups will be performed using the full netgroup tuple: host name, user name and domain (if one is set). Historically, sudo only matched the user name and domain for netgroups used in a `User_List` and only matched the host name and domain for netgroups used in a `Host_List`. This flag is off by default.

`noexec` If set, all commands run via sudo will behave as if the `NOEXEC` tag has been set, unless overridden by an `EXEC` tag. See the description of `EXEC` and `NOEXEC` above as well as the Preventing shell escapes section at the end of this manual. This flag is off by default.

`pam_acct_mgmt` On systems that use PAM for authentication, sudo will perform PAM account validation for the invoking user by default. The actual checks performed depend on which PAM modules are configured. If enabled, account validation will be performed regardless of whether or not a password is required. This flag is on by default.

This setting is only supported by version 1.8.28 or higher.

`pam_session` On systems that use PAM for authentication, sudo will create a new PAM session for the command to be run in. Unless sudo is given the `-i` or `-s` options, PAM session modules are run with the `?silent?` flag enabled. This prevents last login information from being displayed for every command on some systems. Disabling `pam_session` may be needed on older PAM implementations or on operating systems where opening a PAM session changes the `utmp` or `wtmp` files. If PAM

session support is disabled, resource limits may not be updated for the command being run. If `pam_session`, `pam_setcred`, and `use_pty` are disabled and I/O logging has not been configured, `sudo` will execute the command directly instead of running it as a child process. This flag is on by default.

This setting is only supported by version 1.8.7 or higher.

`pam_setcred` On systems that use PAM for authentication, `sudo` will attempt to establish credentials for the target user by default, if supported by the underlying authentication system. One example of a credential is a Kerberos ticket. If `pam_session`, `pam_setcred`, and `use_pty` are disabled and I/O logging has not been configured, `sudo` will execute the command directly instead of running it as a child process. This flag is on by default.

This setting is only supported by version 1.8.8 or higher.

`passprompt_override`

If set, the prompt specified by `passprompt` or the `SUDO_PROMPT` environment variable will always be used and will replace the prompt provided by a PAM module or other authentication method. This flag is off by default.

`path_info` Normally, `sudo` will tell the user when a command could not be found in their `PATH` environment variable. Some sites may wish to disable this as it could be used to gather information on the location of executables that the normal user does not have access to. The disadvantage is that if the executable is simply not in the user's `PATH`, `sudo` will tell the user that they are not allowed to run it, which can be confusing. This flag is on by default.

`preserve_groups` By default, `sudo` will initialize the group vector to the list of groups the target user is in. When `preserve_groups` is set, the user's existing group vector is left unaltered. The real and effective group-IDs, however, are still set to match the target user. This flag is off by default.

`pwfeedback` By default, `sudo` reads the password like most other Unix programs, by turning off echo until the user hits the return (or enter) key.

Some users become confused by this as it appears to them that sudo has hung at this point. When pwfeedback is set, sudo will provide visual feedback when the user presses a key. Note that this does have a security impact as an onlooker may be able to determine the length of the password being entered. This flag is off by default.

requiretty If set, sudo will only run when the user is logged in to a real tty. When this flag is set, sudo can only be run from a login session and not via other means such as cron(8) or cgi-bin scripts. This flag is off by default.

root_sudo If set, root is allowed to run sudo too. Disabling this prevents users from chaining sudo commands to get a root shell by doing something like `sudo sudo /bin/sh`. Note, however, that turning off root_sudo will also prevent root from running sudoedit. Disabling root_sudo provides no real additional security; it exists purely for historical reasons. This flag is on by default.

rootpw If set, sudo will prompt for the root password instead of the password of the invoking user when running a command or editing a file. This flag is off by default.

runas_allow_unknown_id

If enabled, allow matching of runas user and group IDs that are not present in the password or group databases. In addition to explicitly matching unknown user or group IDs in a Runas_List, this option also allows the ALL alias to match unknown IDs. This flag is off by default.

This setting is only supported by version 1.8.30 or higher. Older versions of sudo always allowed matching of unknown user and group IDs.

runas_check_shell

If enabled, sudo will only run commands as a user whose shell appears in the `/etc/shells` file, even if the invoking user's Runas_List would otherwise permit it. If no `/etc/shells` file is present, a system-dependent list of built-in default shells is used. On many operating systems, system users such as `bin`, do

not have a valid shell and this flag can be used to prevent com?

mands from being run as those users. This flag is off by default.

This setting is only supported by version 1.8.30 or higher.

runaspw If set, sudo will prompt for the password of the user defined by the `runas_default` option (defaults to root) instead of the password of the invoking user when running a command or editing a file.

This flag is off by default.

set_home If enabled and sudo is invoked with the `-s` option, the HOME environment variable will be set to the home directory of the target user (which is the root user unless the `-u` option is used). This flag is largely obsolete and has no effect unless the `env_reset` flag has been disabled or HOME is present in the `env_keep` list, both of which are strongly discouraged. This flag is off by default.

set_logname Normally, sudo will set the LOGNAME and USER environment variables to the name of the target user (usually root unless the `-u` option is given). However, since some programs (including the RCS revision control system) use LOGNAME to determine the real identity of the user, it may be desirable to change this behavior. This can be done by negating the `set_logname` option. Note that `set_logname` will have no effect if the `env_reset` option has not been disabled and the `env_keep` list contains LOGNAME or USER. This flag is on by default.

set_utm When enabled, sudo will create an entry in the utmp (or utmpx) file when a pseudo-terminal is allocated. A pseudo-terminal is allocated by sudo when it is running in a terminal and one or more of the `log_input`, `log_output` or `use_pty` flags is enabled. By default, the new entry will be a copy of the user's existing utmp entry (if any), with the `tty`, `time`, `type` and `pid` fields updated. This flag is on by default.

setenv Allow the user to disable the `env_reset` option from the command line via the `-E` option. Additionally, environment variables set via the command line are not subject to the restrictions imposed by

env_check, env_delete, or env_keep. As such, only trusted users should be allowed to set variables in this manner. This flag is off by default.

shell_noargs If set and sudo is invoked with no arguments it acts as if the -s option had been given. That is, it runs a shell as root (the shell is determined by the SHELL environment variable if it is set, falling back on the shell listed in the invoking user's /etc/passwd entry if not). This flag is off by default.

stay_setuid Normally, when sudo executes a command the real and effective UIDs are set to the target user (root by default). This option changes that behavior such that the real UID is left as the invoking user's UID. In other words, this makes sudo act as a set-user-ID wrapper. This can be useful on systems that disable some potentially dangerous functionality when a program is run set-user-ID. This option is only effective on systems that support either the setreuid(2) or setresuid(2) system call. This flag is off by default.

sudoedit_checkdir

If set, sudoedit will check all directory components of the path to be edited for writability by the invoking user. Symbolic links will not be followed in writable directories and sudoedit will refuse to edit a file located in a writable directory. These restrictions are not enforced when sudoedit is run by root. On some systems, if all directory components of the path to be edited are not readable by the target user, sudoedit will be unable to edit the file. This flag is on by default.

This setting was first introduced in version 1.8.15 but initially suffered from a race condition. The check for symbolic links in writable intermediate directories was added in version 1.8.16.

sudoedit_follow By default, sudoedit will not follow symbolic links when opening files. The sudoedit_follow option can be enabled to allow sudoedit to open symbolic links. It may be overridden on a per-command basis by the FOLLOW and NOFOLLOW tags. This flag is off by default. This setting is only supported by version 1.8.15 or higher.

`syslog_pid` When logging via `syslog(3)`, include the process ID in the log entry. This flag is off by default.

This setting is only supported by version 1.8.21 or higher.

`targetpw` If set, `sudo` will prompt for the password of the user specified by the `-u` option (defaults to `root`) instead of the password of the invoking user when running a command or editing a file. Note that this flag precludes the use of a user-ID not listed in the `passwd` database as an argument to the `-u` option. This flag is off by default.

`tty_tickets` If set, users must authenticate on a per-tty basis. With this flag enabled, `sudo` will use a separate record in the time stamp file for each terminal. If disabled, a single record is used for all login sessions.

This option has been superseded by the `timestamp_type` option.

`umask_override` If set, `sudo` will set the `umask` as specified in the `sudoers` file without modification. This makes it possible to specify a `umask` in the `sudoers` file that is more permissive than the user's own `umask` and matches historical behavior. If `umask_override` is not set, `sudo` will set the `umask` to be the union of the user's `umask` and what is specified in `sudoers`. This flag is off by default.

`use_netgroups` If set, `netgroups` (prefixed with `?+?`), may be used in place of a user or host. For LDAP-based `sudoers`, `netgroup` support requires an expensive sub-string match on the server unless the `NETGROUP_BASE` directive is present in the `/etc/ldap.conf` file. If `netgroups` are not needed, this option can be disabled to reduce the load on the LDAP server. This flag is on by default.

`use_pty` If set, and `sudo` is running in a terminal, the command will be run in a pseudo-terminal (even if no I/O logging is being done). If the `sudo` process is not attached to a terminal, `use_pty` has no effect.

A malicious program run under `sudo` may be capable of injecting commands into the user's terminal or running a background process that retains access to the user's terminal device even after the main

program has finished executing. By running the command in a separate pseudo-terminal, this attack is no longer possible. This flag is off by default.

user_command_timeouts

If set, the user may specify a timeout on the command line. If the timeout expires before the command has exited, the command will be terminated. If a timeout is specified both in the sudoers file and on the command line, the smaller of the two timeouts will be used.

See the Timeout_Spec section for a description of the timeout syntax. This flag is off by default.

This setting is only supported by version 1.8.20 or higher.

utmp_runas If set, sudo will store the name of the runas user when updating the utmp (or utmpx) file. By default, sudo stores the name of the invoking user. This flag is off by default.

visiblepw By default, sudo will refuse to run if the user must enter a password but it is not possible to disable echo on the terminal. If the visiblepw flag is set, sudo will prompt for a password even when it would be visible on the screen. This makes it possible to run things like `ssh somehost sudo ls` since by default, `ssh(1)` does not allocate a tty when running a command. This flag is off by default.

Integers:

closefrom Before it executes a command, sudo will close all open file descriptors other than standard input, standard output and standard error (ie: file descriptors 0-2). The closefrom option can be used to specify a different file descriptor at which to start closing.

The default is 3.

command_timeout The maximum amount of time a command is allowed to run before it is terminated. See the Timeout_Spec section for a description of the timeout syntax.

This setting is only supported by version 1.8.20 or higher.

maxseq The maximum sequence number that will be substituted for the `%{seq}` escape in the I/O log file (see the `iolog_dir` description

below for more information). While the value substituted for `%(seq)?` is in base 36, `maxseq` itself should be expressed in decimal. Values larger than 2176782336 (which corresponds to the base 36 sequence number `ZZZZZZ?`) will be silently truncated to 2176782336. The default value is 2176782336.

Once the local sequence number reaches the value of `maxseq`, it will `roll over?` to zero, after which `sudoers` will truncate and re-use any existing I/O log path names.

This setting is only supported by version 1.8.7 or higher.

`passwd_tries` The number of tries a user gets to enter his/her password before `sudo` logs the failure and exits. The default is 3.

`syslog_maxlen` On many systems, `syslog(3)` has a relatively small log buffer. IETF RFC 5424 states that syslog servers must support messages of at least 480 bytes and should support messages up to 2048 bytes. By default, `sudoers` creates log messages up to 980 bytes which corresponds to the historic BSD syslog implementation which used a 1024 byte buffer to store the message, date, hostname and program name. To prevent syslog messages from being truncated, `sudoers` will split up log messages that are larger than `syslog_maxlen` bytes. When a message is split, additional parts will include the string `?(command continued)?` after the user name and before the continued command line arguments.

This setting is only supported by version 1.8.19 or higher.

Integers that can be used in a boolean context:

`loglinelen` Number of characters per line for the file log. This value is used to decide when to wrap lines for nicer log files. This has no effect on the syslog log file, only the file log. The default is 80 (use 0 or negate the option to disable word wrap).

`passwd_timeout` Number of minutes before the sudo password prompt times out, or 0 for no timeout. The timeout may include a fractional component if minute granularity is insufficient, for example 2.5. The default is 0.

`timestamp_timeout`

Number of minutes that can elapse before sudo will ask for a password again. The timeout may include a fractional component if minute granularity is insufficient, for example 2.5. The default is 15.

Set this to 0 to always prompt for a password. If set to a value less than 0 the user's time stamp will not expire until the system is rebooted. This can be used to allow users to create or delete their own time stamps via `?sudo -v?` and `?sudo -k?` respectively.

umask File mode creation mask to use when running the command. Negate this option or set it to 0777 to prevent sudoers from changing the umask. Unless the `umask_override` flag is set, the actual umask will be the union of the user's umask and the value of the umask setting, which defaults to 0022. This guarantees that sudo never lowers the umask when running a command.

If umask is explicitly set in sudoers, it will override any umask setting in PAM or `login.conf`. If umask is not set in sudoers, the umask specified by PAM or `login.conf` will take precedence. The umask setting in PAM is not used for `sudoedit`, which does not create a new PAM session.

Strings:

authfail_message Message that is displayed after a user fails to authenticate. The message may include the `?%d?` escape which will expand to the number of failed password attempts. If set, it overrides the default message, `%d incorrect password attempt(s)`.

badpass_message Message that is displayed if a user enters an incorrect password. The default is `Sorry, try again.` unless insults are enabled.

editor A colon (?:) separated list of editors path names used by `sudoedit` and `visudo`. For `sudoedit`, this list is used to find an editor when none of the `SUDO_EDITOR`, `VISUAL` or `EDITOR` environment variables are set to an editor that exists and is executable. For `visudo`, it is used as a white list of allowed editors; `visudo` will choose the editor that matches the user's `SUDO_EDITOR`, `VISUAL` or `EDITOR` environment variable if possible, or the first editor in the list that exists and is executable if not. Unless invoked as `sudoedit`, `sudo`

does not preserve the SUDO_EDITOR, VISUAL or EDITOR environment variables unless they are present in the env_keep list or the env_reset option is disabled. The default is /usr/bin/editor.

iolog_dir The top-level directory to use when constructing the path name for the input/output log directory. Only used if the log_input or log_output options are enabled or when the LOG_INPUT or LOG_OUTPUT tags are present for a command. The session sequence number, if any, is stored in the directory. The default is /var/log/sudo-io.

The following percent (???) escape sequences are supported:

%{seq}

expanded to a monotonically increasing base-36 sequence number, such as 0100A5, where every two digits are used to form a new directory, e.g., 01/00/A5

%{user}

expanded to the invoking user's login name

%{group}

expanded to the name of the invoking user's real group-ID

%{runas_user}

expanded to the login name of the user the command will be run as (e.g., root)

%{runas_group}

expanded to the group name of the user the command will be run as (e.g., wheel)

%{hostname}

expanded to the local host name without the domain name

%{command}

expanded to the base name of the command being run

In addition, any escape sequences supported by the system's strftime(3) function will be expanded.

To include a literal ??? character, the string %%%? should be used.

iolog_file The path name, relative to iolog_dir, in which to store input/output logs when the log_input or log_output options are enabled or when the LOG_INPUT or LOG_OUTPUT tags are present for a command.

Note that `iolog_file` may contain directory components. The default is `?%{seq}?`.

See the `iolog_dir` option above for a list of supported percent (`??`) escape sequences.

In addition to the escape sequences, path names that end in six or more Xs will have the Xs replaced with a unique combination of digits and letters, similar to the `mktemp(3)` function.

If the path created by concatenating `iolog_dir` and `iolog_file` already exists, the existing I/O log file will be truncated and overwritten unless `iolog_file` ends in six or more Xs.

`iolog_flush` If set, `sudo` will flush I/O log data to disk after each write instead of buffering it. This makes it possible to view the logs in real-time as the program is executing but may significantly reduce the effectiveness of I/O log compression. This flag is off by default.

This setting is only supported by version 1.8.20 or higher.

`iolog_group` The group name to look up when setting the group-ID on new I/O log files and directories. If `iolog_group` is not set, the primary group-ID of the user specified by `iolog_user` is used. If neither `iolog_group` nor `iolog_user` are set, I/O log files and directories are created with group-ID 0.

This setting is only supported by version 1.8.19 or higher.

`iolog_mode` The file mode to use when creating I/O log files. Mode bits for read and write permissions for owner, group or other are honored, everything else is ignored. The file permissions will always include the owner read and write bits, even if they are not present in the specified mode. When creating I/O log directories, search (execute) bits are added to match the read and write bits specified by `iolog_mode`. Defaults to 0600 (read and write by user only).

This setting is only supported by version 1.8.19 or higher.

`iolog_user` The user name to look up when setting the user and group-IDs on new I/O log files and directories. If `iolog_group` is set, it will be used instead of the user's primary group-ID. By default, I/O log

files and directories are created with user and group-ID 0.

This setting can be useful when the I/O logs are stored on a Network File System (NFS) share. Having a dedicated user own the I/O log files means that sudoers does not write to the log files as user-ID 0, which is usually not permitted by NFS.

This setting is only supported by version 1.8.19 or higher.

lecture_status_dir

The directory in which sudo stores per-user lecture status files.

Once a user has received the lecture, a zero-length file is created in this directory so that sudo will not lecture the user again.

This directory should not be cleared when the system reboots. The default is `/var/lib/sudo/lectured`.

mailsub Subject of the mail sent to the mailto user. The escape `%h` will expand to the host name of the machine. Default is `?*** SECURITY information for %h ***?`.

noexec_file As of sudo version 1.8.1 this option is no longer supported. The path to the noexec file should now be set in the `sudo.conf(5)` file.

pam_login_service

On systems that use PAM for authentication, this is the service name used when the `-i` option is specified. The default value is `?sudo?`. See the description of `pam_service` for more information.

This setting is only supported by version 1.8.8 or higher.

pam_service On systems that use PAM for authentication, the service name specifies the PAM policy to apply. This usually corresponds to an entry in the `pam.conf` file or a file in the `/etc/pam.d` directory. The default value is `?sudo?`.

This setting is only supported by version 1.8.8 or higher.

passprompt The default prompt to use when asking for a password; can be overridden via the `-p` option or the `SUDO_PROMPT` environment variable. The following percent (`%?`) escape sequences are supported:

- `%H` expanded to the local host name including the domain name (only if the machine's host name is fully qualified or the `fqdn` option is set)

%h expanded to the local host name without the domain name

%p expanded to the user whose password is being asked for (respects the rootpw, targetpw and runaspw flags in sudoers)

%U expanded to the login name of the user the command will be run as (defaults to root)

%u expanded to the invoking user's login name

%% two consecutive % characters are collapsed into a single % character

On systems that use PAM for authentication, passprompt will only be used if the prompt provided by the PAM module matches the string ?Password: ? or ?username's Password: ?. This ensures that the passprompt setting does not interfere with challenge-response style authentication. The passprompt_override flag can be used to change this behavior.

The default value is ?[sudo] password for %p: ?.

role The default SELinux role to use when constructing a new security context to run the command. The default role may be overridden on a per-command basis in the sudoers file or via command line options. This option is only available when sudo is built with SELinux support.

runas_default The default user to run commands as if the -u option is not specified on the command line. This defaults to root.

sudoers_locale Locale to use when parsing the sudoers file, logging commands, and sending email. Note that changing the locale may affect how sudoers is interpreted. Defaults to ?C?.

timestamp_type sudoers uses per-user time stamp files for credential caching. The timestamp_type option can be used to specify the type of time stamp record used. It has the following possible values:

global A single time stamp record is used for all of a user's login sessions, regardless of the terminal or parent process ID. An additional record is used to serialize password prompts when sudo is used multiple times in a pipeline, but this does not affect authentication.

ppid A single time stamp record is used for all processes with the same parent process ID (usually the shell). Commands run from the same shell (or other common parent process) will not require a password for `timestamp_timeout` minutes (15 by default). Commands run via `sudo` with a different parent process ID, for example from a shell script, will be authenticated separately.

tty One time stamp record is used for each terminal, which means that a user's login sessions are authenticated separately. If no terminal is present, the behavior is the same as `ppid`. Commands run from the same terminal will not require a password for `timestamp_timeout` minutes (15 by default).

kernel The time stamp is stored in the kernel as an attribute of the terminal device. If no terminal is present, the behavior is the same as `ppid`. Negative `timestamp_timeout` values are not supported and positive values are limited to a maximum of 60 minutes. This is currently only supported on OpenBSD.

The default value is `tty`.

This setting is only supported by version 1.8.21 or higher.

timestampdir The directory in which `sudo` stores its time stamp files. This directory should be cleared when the system reboots. The default is `/run/sudo/ts`.

timestampowner The owner of the lecture status directory, time stamp directory and all files stored therein. The default is `root`.

type The default SELinux type to use when constructing a new security context to run the command. The default type may be overridden on a per-command basis in the `sudoers` file or via command line options. This option is only available when `sudo` is built with SELinux support.

Strings that can be used in a boolean context:

env_file The `env_file` option specifies the fully qualified path to a file con?

taining variables to be set in the environment of the program being run. Entries in this file should either be of the form `?VARIABLE=value?` or `?export VARIABLE=value?`. The value may optionally be surrounded by single or double quotes. Variables in this file are only added if the variable does not already exist in the environment. This file is considered to be part of the security policy, its contents are not subject to other sudo environment restrictions such as `env_keep` and `env_check`.

`exempt_group` Users in this group are exempt from password and PATH requirements.

The group name specified should not include a % prefix. This is not set by default.

`fdexec` Determines whether sudo will execute a command by its path or by an open file descriptor. It has the following possible values:

`always` Always execute by file descriptor.

`never` Never execute by file descriptor.

`digest_only`

Only execute by file descriptor if the command has an associated digest in the sudoers file.

The default value is `digest_only`. This avoids a time of check versus time of use race condition when the command is located in a directory writable by the invoking user.

Note that `fdexec` will change the first element of the argument vector for scripts (`$0` in the shell) due to the way the kernel runs script interpreters. Instead of being a normal path, it will refer to a file descriptor. For example, `/dev/fd/4` on Solaris and `/proc/self/fd/4` on Linux. A workaround is to use the `SUDO_COMMAND` environment variable instead.

The `fdexec` setting is only used when the command is matched by path name. It has no effect if the command is matched by the built-in ALL alias.

This setting is only supported by version 1.8.20 or higher. If the operating system does not support the `fexecve(2)` system call, this setting has no effect.

`group_plugin` A string containing a sudoers group plugin with optional arguments.

The string should consist of the plugin path, either fully-qualified or relative to the `/usr/lib/sudo` directory, followed by any configuration arguments the plugin requires. These arguments (if any) will be passed to the plugin's initialization function. If arguments are present, the string must be enclosed in double quotes (`""`).

For more information see `GROUP PROVIDER PLUGINS`.

`lecture` This option controls when a short lecture will be printed along with the password prompt. It has the following possible values:

`always` Always lecture the user.

`never` Never lecture the user.

`once` Only lecture the user the first time they run sudo.

If no value is specified, a value of `once` is implied. Negating the option results in a value of `never` being used. The default value is `never`.

`lecture_file` Path to a file containing an alternate sudo lecture that will be used in place of the standard lecture if the named file exists. By default, sudo uses a built-in lecture.

`listpw` This option controls when a password will be required when a user runs sudo with the `-l` option. It has the following possible values:

`all` All the user's sudoers file entries for the current host must have the `NOPASSWD` flag set to avoid entering a password.

`always` The user must always enter a password to use the `-l` option.

`any` At least one of the user's sudoers file entries for the current host must have the `NOPASSWD` flag set to avoid entering a password.

`never` The user need never enter a password to use the `-l` option.

If no value is specified, a value of `any` is implied. Negating the option results in a value of `never` being used. The default value is `any`.

`logfile` Path to the sudo log file (not the syslog log file). Setting a path turns on logging to a file; negating this option turns it off. By default, sudo logs via syslog.

`mailerflags` Flags to use when invoking mailer. Defaults to `-t`.

mailerpath Path to mail program used to send warning mail. Defaults to the path to sendmail found at configure time.

mailfrom Address to use for the `?from?` address when sending warning and error mail. The address should be enclosed in double quotes (`"`) to protect against sudo interpreting the `@` sign. Defaults to the name of the user running sudo.

mailto Address to send warning and error mail to. The address should be enclosed in double quotes (`"`) to protect against sudo interpreting the `@` sign. Defaults to root.

restricted_env_file

The `restricted_env_file` option specifies the fully qualified path to a file containing variables to be set in the environment of the program being run. Entries in this file should either be of the form `?VARIABLE=value?` or `?export VARIABLE=value?`. The value may optionally be surrounded by single or double quotes. Variables in this file are only added if the variable does not already exist in the environment. Unlike `env_file`, the file's contents are not trusted and are processed in a manner similar to that of the invoking user's environment. If `env_reset` is enabled, variables in the file will only be added if they are matched by either the `env_check` or `env_keep` list. If `env_reset` is disabled, variables in the file are added as long as they are not matched by the `env_delete` list. In either case, the contents of `restricted_env_file` are processed before the contents of `env_file`.

secure_path If set, sudo will use this value in place of the user's `PATH` environment variable. This option can be used to reset the `PATH` to a known good value that contains directories for system administrator commands such as `/usr/sbin`.

Users in the group specified by the `exempt_group` option are not affected by `secure_path`. This option is not set by default.

syslog Syslog facility if syslog is being used for logging (negate to disable syslog logging). Defaults to `authpriv`.

The following syslog facilities are supported: `authpriv` (if your OS supports it), `auth`, `daemon`, `user`, `local0`, `local1`, `local2`, `local3`,

local4, local5, local6, and local7.

syslog_badpri

Syslog priority to use when the user is not allowed to run a command or when authentication is unsuccessful. Defaults to alert.

The following syslog priorities are supported: alert, crit, debug, emerg, err, info, notice, warning, and none. Negating the option or setting it to a value of none will disable logging of unsuccessful commands.

syslog_goodpri

Syslog priority to use when the user is allowed to run a command and authentication is successful. Defaults to notice.

See syslog_badpri for the list of supported syslog priorities. Negating the option or setting it to a value of none will disable logging of successful commands.

verifypw This option controls when a password will be required when a user runs sudo with the -v option. It has the following possible values:

all All the user's sudoers file entries for the current host must have the NOPASSWD flag set to avoid entering a password.

always The user must always enter a password to use the -v option.

any At least one of the user's sudoers file entries for the current host must have the NOPASSWD flag set to avoid entering a password.

never The user need never enter a password to use the -v option.

If no value is specified, a value of all is implied. Negating the option results in a value of never being used. The default value is all.

Lists that can be used in a boolean context:

env_check Environment variables to be removed from the user's environment unless they are considered "safe". For all variables except TZ,

"safe" means that the variable's value does not contain any % or / characters. This can be used to guard against printf-style format vulnerabilities in poorly-written programs. The TZ variable is considered unsafe if any of the following are true:

? It consists of a fully-qualified path name, optionally prefixed

with a colon (:?), that does not match the location of the zoneinfo directory.

? It contains a .. path element.

? It contains white space or non-printable characters.

? It is longer than the value of PATH_MAX.

The argument may be a double-quoted, space-separated list or a single value without double-quotes. The list can be replaced, added to, deleted from, or disabled by using the =, +=, -=, and ! operators respectively. Regardless of whether the env_reset option is enabled or disabled, variables specified by env_check will be preserved in the environment if they pass the aforementioned check. The global list of environment variables to check is displayed when sudo is run by root with the -V option.

env_delete Environment variables to be removed from the user's environment when the env_reset option is not in effect. The argument may be a double-quoted, space-separated list or a single value without double-quotes. The list can be replaced, added to, deleted from, or disabled by using the =, +=, -=, and ! operators respectively. The global list of environment variables to remove is displayed when sudo is run by root with the -V option. Note that many operating systems will remove potentially dangerous variables from the environment of any set-user-ID process (such as sudo).

env_keep Environment variables to be preserved in the user's environment when the env_reset option is in effect. This allows fine-grained control over the environment sudo-spawned processes will receive. The argument may be a double-quoted, space-separated list or a single value without double-quotes. The list can be replaced, added to, deleted from, or disabled by using the =, +=, -=, and ! operators respectively. The global list of variables to keep is displayed when sudo is run by root with the -V option.

Preserving the HOME environment variable has security implications since many programs use it when searching for configuration or data files. Adding HOME to env_keep may enable a user to run unre-

stricted commands via sudo and is strongly discouraged. Users wishing to edit files with sudo should run `sudoedit` (or `sudo -e`) to get their accustomed editor configuration instead of invoking the editor directly.

GROUP PROVIDER PLUGINS

The sudoers plugin supports its own plugin interface to allow non-Unix group lookups which can query a group source other than the standard Unix group database. This can be used to implement support for the `nonunix_group` syntax described earlier.

Group provider plugins are specified via the `group_plugin` setting. The argument to `group_plugin` should consist of the plugin path, either fully-qualified or relative to the `/usr/lib/sudo` directory, followed by any configuration options the plugin requires. These options (if specified) will be passed to the plugin's initialization function. If options are present, the string must be enclosed in double quotes (`"`).

The following group provider plugins are installed by default:

`group_file`

The `group_file` plugin supports an alternate group file that uses the same syntax as the `/etc/group` file. The path to the group file should be specified as an option to the plugin. For example, if the group file to be used is `/etc/sudo-group`:

```
Defaults group_plugin="group_file.so /etc/sudo-group"
```

`system_group`

The `system_group` plugin supports group lookups via the standard C library functions `getgrnam()` and `getgrid()`. This plugin can be used in instances where the user belongs to groups not present in the user's supplemental group vector. This plugin takes no options:

```
Defaults group_plugin=system_group.so
```

The group provider plugin API is described in detail in `sudo_plugin(5)`.

LOG FORMAT

sudoers can log events using either `syslog(3)` or a simple log file. The log format is almost identical in both cases.

Accepted command log entries

Commands that sudo runs are logged using the following format (split into multiple lines for readability):

```
date hostname progame: username : TTY=ttyname ; PWD=cwd ; \
```

```
USER=runasuser ; GROUP=runasgroup ; TSID=logid ; \
```

```
ENV=env_vars COMMAND=command
```

Where the fields are as follows:

date The date the command was run. Typically, this is in the format ?MMM, DD, HH:MM:SS?. If logging via syslog(3), the actual date format is controlled by the syslog daemon. If logging to a file and the log_year option is enabled, the date will also include the year.

hostname The name of the host sudo was run on. This field is only present when logging via syslog(3).

progame The name of the program, usually sudo or sudoedit. This field is only present when logging via syslog(3).

username The login name of the user who ran sudo.

ttyname The short name of the terminal (e.g., ?console?, ?tty01?, or ?pts/0?) sudo was run on, or ?unknown? if there was no terminal present.

cwd The current working directory that sudo was run in.

runasuser The user the command was run as.

runasgroup The group the command was run as if one was specified on the command line.

logid An I/O log identifier that can be used to replay the command's output. This is only present when the log_input or log_output option is enabled.

env_vars A list of environment variables specified on the command line, if specified.

command The actual command that was executed.

Messages are logged using the locale specified by sudoers_locale, which defaults to the ?C? locale.

Denied command log entries

If the user is not allowed to run the command, the reason for the denial will follow the user name. Possible reasons include:

user NOT in sudoers

The user is not listed in the sudoers file.

user NOT authorized on host

The user is listed in the sudoers file but is not allowed to run commands on the host.

command not allowed

The user is listed in the sudoers file for the host but they are not allowed to run the specified command.

3 incorrect password attempts

The user failed to enter their password after 3 tries. The actual number of tries will vary based on the number of failed attempts and the value of the passwd_tries option.

a password is required

The -n option was specified but a password was required.

sorry, you are not allowed to set the following environment variables

The user specified environment variables on the command line that were not allowed by sudoers.

Error log entries

If an error occurs, sudoers will log a message and, in most cases, send a message to the administrator via email. Possible errors include:

parse error in /etc/sudoers near line N

sudoers encountered an error when parsing the specified file. In some cases, the actual error may be one line above or below the line number listed, depending on the type of error.

problem with defaults entries

The sudoers file contains one or more unknown Defaults settings. This does not prevent sudo from running, but the sudoers file should be checked using visudo.

timestamp owner (username): No such user

The time stamp directory owner, as specified by the timestampowner setting, could not be found in the password database.

unable to open/read /etc/sudoers

The sudoers file could not be opened for reading. This can happen when the sudoers file is located on a remote file system that maps user-ID 0 to a different value.

Normally, sudoers tries to open the sudoers file using group permissions to avoid this problem. Consider either changing the ownership of /etc/sudoers or adding an argument like ?sudoers_uid=N? (where ?N? is the user-ID that owns the sudoers file)

to the end of the sudoers Plugin line in the sudo.conf(5) file.

unable to stat /etc/sudoers

The /etc/sudoers file is missing.

/etc/sudoers is not a regular file

The /etc/sudoers file exists but is not a regular file or symbolic link.

/etc/sudoers is owned by uid N, should be 0

The sudoers file has the wrong owner. If you wish to change the sudoers file owner, please add ?sudoers_uid=N? (where ?N? is the user-ID that owns the sudoers file) to the sudoers Plugin line in the sudo.conf(5) file.

/etc/sudoers is world writable

The permissions on the sudoers file allow all users to write to it. The sudoers file must not be world-writable, the default file mode is 0440 (readable by owner and group, writable by none). The default mode may be changed via the ?sudoers_mode? option to the sudoers Plugin line in the sudo.conf(5) file.

/etc/sudoers is owned by gid N, should be 1

The sudoers file has the wrong group ownership. If you wish to change the sudoers file group ownership, please add ?sudoers_gid=N? (where ?N? is the group-ID that owns the sudoers file) to the sudoers Plugin line in the sudo.conf(5) file.

unable to open /run/sudo/ts/username

sudoers was unable to read or create the user's time stamp file. This can happen when timestampowner is set to a user other than root and the mode on /run/sudo is not searchable by group or other. The default mode for /run/sudo is 0711.

unable to write to /run/sudo/ts/username

sudoers was unable to write to the user's time stamp file.

/run/sudo/ts is owned by uid X, should be Y

The time stamp directory is owned by a user other than timestampowner. This can occur when the value of timestampowner has been changed. sudoers will ignore the time stamp directory until the owner is corrected.

/run/sudo/ts is group writable

The time stamp directory is group-writable; it should be writable only by timestampowner. The default mode for the time stamp directory is 0700. sudoers will ignore the time stamp directory until the mode is corrected.

By default, sudoers logs messages via syslog(3). The date, hostname, and progname fields are added by the system's syslog() function, not sudoers itself. As such, they may vary in format on different systems.

The maximum size of syslog messages varies from system to system. The syslog_maxlen setting can be used to change the maximum syslog message size from the default value of 980 bytes. For more information, see the description of syslog_maxlen.

Notes on logging to a file

If the logfile option is set, sudoers will log to a local file, such as /var/log/sudo. When logging to a file, sudoers uses a format similar to syslog(3), with a few important differences:

1. The progname and hostname fields are not present.
2. If the log_year option is enabled, the date will also include the year.
3. Lines that are longer than loglinelen characters (80 by default) are word-wrapped and continued on the next line with a four character indent. This makes entries easier to read for a human being, but makes it more difficult to use grep(1) on the log files. If the loglinelen option is set to 0 (or negated with a !?), word wrap will be disabled.

I/O LOG FILES

When I/O logging is enabled, sudo will run the command in a pseudo-terminal and log all user input and/or output, depending on which options are enabled. I/O is logged to the directory specified by the iolog_dir option (/var/log/sudo-io by default) using a unique session ID that is included in the sudo log line, prefixed with ?TSID=?.

The iolog_file option may be used to control the format of the session ID.

Each I/O log is stored in a separate directory that contains the following files:

log A text file containing information about the command. The first line consists of the following colon-delimited fields: the time the command was run, the name of the user who ran sudo, the name of the target user, the name of the target group (optional), the terminal that sudo was run from, and the number of lines and columns of the terminal. The second and third lines contain the working directory the command was run from and the path name of the command itself (with arguments if present).

timing Timing information used to replay the session. Each line consists of the I/O log entry type and amount of time since the last entry, followed by

type-specific data. The I/O log entry types and their corresponding type-specific data are:

- 0 standard input, number of bytes in the entry
- 1 standard output, number of bytes in the entry
- 2 standard error, number of bytes in the entry
- 3 terminal input, number of bytes in the entry
- 4 terminal output, number of bytes in the entry
- 5 window change, new number lines and columns
- 6 bug compatibility for sudo 1.8.7 terminal output
- 7 command suspend or resume, signal received

`tt Yin` Raw input from the user's terminal, exactly as it was received. No post-processing is performed. For manual viewing, you may wish to convert carriage return characters in the log to line feeds. For example: `?gunzip -c tt Yin | tr "\r" "\n"?`

`std In` The standard input when no terminal is present, or input redirected from a pipe or file.

`tt Yout` Output from the pseudo-terminal (what the command writes to the screen). Note that terminal-specific post-processing is performed before the data is logged. This means that, for example, line feeds are usually converted to line feed/carriage return pairs and tabs may be expanded to spaces.

`std out` The standard output when no terminal is present, or output redirected to a pipe or file.

`std err` The standard error redirected to a pipe or file.

All files other than log are compressed in gzip format unless the `compress_io` flag has been disabled. Due to buffering, it is not normally possible to display the I/O logs in real-time as the program is executing. The I/O log data will not be complete until the program run by sudo has exited or has been terminated by a signal. The `iolog_flush` flag can be used to disable buffering, in which case I/O log data is written to disk as soon as it is available. The output portion of an I/O log file can be viewed with the `sudoreplay(8)` utility, which can also be used to list or search the available logs.

Note that user input may contain sensitive information such as passwords (even if they are not echoed to the screen), which will be stored in the log file unencrypted.

In most cases, logging the command output via `log_output` or `LOG_OUTPUT` is all that is required.

Since each session's I/O logs are stored in a separate directory, traditional log rotation utilities cannot be used to limit the number of I/O logs. The simplest way to limit the number of I/O is by setting the `maxseq` option to the maximum number of logs you wish to store. Once the I/O log sequence number reaches `maxseq`, it will be reset to zero and sudoers will truncate and re-use any existing I/O logs.

FILES

<code>/etc/sudo.conf</code>	Sudo front end configuration
<code>/etc/sudoers</code>	List of who can run what
<code>/etc/group</code>	Local groups file
<code>/etc/netgroup</code>	List of network groups
<code>/var/log/sudo-io</code>	I/O log files
<code>/run/sudo/ts</code>	Directory containing time stamps for the sudoers security policy
<code>/var/lib/sudo/lectured</code>	Directory containing lecture status files for the sudoers security policy
<code>/etc/environment</code>	Initial environment for <code>-i</code> mode on AIX and Linux systems

EXAMPLES

Below are example sudoers file entries. Admittedly, some of these are a bit contrived. First, we allow a few environment variables to pass and then define our aliases:

```
# Run X applications through sudo; HOME is used to find the
# .Xauthority file. Note that other programs use HOME to find
# configuration files and this may lead to privilege escalation!
```

```
Defaults env_keep += "DISPLAY HOME"
```

```
# User alias specification
```

```
User_Alias FULLTIMERS = millert, mikef, dowdy
```

```
User_Alias PARTTIMERS = bostley, jwfox, crawl
```

```
User_Alias WEBMASTERS = will, wendy, wim
```

```
# Runas alias specification
```

```
Runas_Alias OP = root, operator
```

```
Runas_Alias DB = oracle, sybase
```

```

Runas_Alias  ADMINGRP = adm, oper
# Host alias specification
Host_Alias   SPARC = bigtime, eclipse, moet, anchor :\
             SGI = grolsch, dandelion, black :\
             ALPHA = widget, thalamus, foobar :\
             HPPA = boa, nag, python
Host_Alias   CUNETS = 128.138.0.0/255.255.0.0
Host_Alias   CSNETS = 128.138.243.0, 128.138.204.0/24, 128.138.242.0
Host_Alias   SERVERS = master, mail, www, ns
Host_Alias   CDROM = orion, perseus, hercules
# Cmnd alias specification
Cmnd_Alias   DUMPS = /usr/bin/mt, /usr/sbin/dump, /usr/sbin/rdump,\
                 /usr/sbin/restore, /usr/sbin/rrestore,\
                 sha224:0GomF8mNN3wIDt1HD9XldjJ3SNgpFdbjO1+Nsq== \
                 /home/operator/bin/start_backups
Cmnd_Alias   KILL = /usr/bin/kill
Cmnd_Alias   PRINTING = /usr/sbin/lpc, /usr/bin/lprm
Cmnd_Alias   SHUTDOWN = /usr/sbin/shutdown
Cmnd_Alias   HALT = /usr/sbin/halt
Cmnd_Alias   REBOOT = /usr/sbin/reboot
Cmnd_Alias   SHELLS = /usr/bin/sh, /usr/bin/csh, /usr/bin/ksh,\
                     /usr/local/bin/tcsh, /usr/bin/rsh,\
                     /usr/local/bin/zsh
Cmnd_Alias   SU = /usr/bin/su
Cmnd_Alias   PAGERS = /usr/bin/more, /usr/bin/pg, /usr/bin/less

```

Here we override some of the compiled in default values. We want sudo to log via syslog(3) using the auth facility in all cases. We don't want to subject the full time staff to the sudo lecture, user millert need not give a password, and we don't want to reset the LOGNAME or USER environment variables when running commands as root. Additionally, on the machines in the SERVERS Host_Alias, we keep an additional local log file and make sure we log the year in each log line since the log entries will be kept around for several years. Lastly, we disable shell escapes for the commands in the PAGERS Cmnd_Alias (/usr/bin/more, /usr/bin/pg and /usr/bin/less). Note

that this will not effectively constrain users with sudo ALL privileges.

```
# Override built-in defaults
```

```
Defaults          syslog=auth
```

```
Defaults>root     !set_logname
```

```
Defaults:FULLTIMERS !lecture
```

```
Defaults:millert  !authenticate
```

```
Defaults@SERVERS  log_year, logfile=/var/log/sudo.log
```

```
Defaults!PAGERS   noexec
```

The User specification is the part that actually determines who may run what.

```
root             ALL = (ALL) ALL
```

```
%wheel          ALL = (ALL) ALL
```

We let root and any user in group wheel run any command on any host as any user.

```
FULLTIMERS      ALL = NOPASSWD: ALL
```

Full time sysadmins (millert, mikef, and dowdy) may run any command on any host without authenticating themselves.

```
PARTTIMERS      ALL = ALL
```

Part time sysadmins (bostley, jwfox, and crawl) may run any command on any host but they must authenticate themselves first (since the entry lacks the NOPASSWD tag).

```
jack            CSNETS = ALL
```

The user jack may run any command on the machines in the CSNETS alias (the networks 128.138.243.0, 128.138.204.0, and 128.138.242.0). Of those networks, only 128.138.204.0 has an explicit netmask (in CIDR notation) indicating it is a class C network. For the other networks in CSNETS, the local machine's netmask will be used during matching.

```
lisa            CUNETS = ALL
```

The user lisa may run any command on any host in the CUNETS alias (the class B network 128.138.0.0).

```
operator        ALL = DUMPS, KILL, SHUTDOWN, HALT, REBOOT, PRINTING,\  
                sudoedit /etc/printcap, /usr/oper/bin/
```

The operator user may run commands limited to simple maintenance. Here, those are commands related to backups, killing processes, the printing system, shutting down the system, and any commands in the directory /usr/oper/bin/. Note that one command in the DUMPS Cmnd_Alias includes a sha224 digest, /home/operator/bin/start_backups.

This is because the directory containing the script is writable by the operator user.

If the script is modified (resulting in a digest mismatch) it will no longer be possible to run it via sudo.

```
joe      ALL = /usr/bin/su operator
```

The user joe may only su(1) to operator.

```
pete     HPPA = /usr/bin/passwd [A-Za-z]*, !/usr/bin/passwd *root*
```

```
%opers   ALL = (: ADMINGRP) /usr/sbin/
```

Users in the `opers` group may run commands in `/usr/sbin/` as themselves with any group in the `ADMINGRP` `Runas_Alias` (the `adm` and `oper` groups).

The user `pete` is allowed to change anyone's password except for root on the HPPA machines. Because command line arguments are matched as a single, concatenated string, the `??` wildcard will match multiple words. This example assumes that `passwd(1)` does not take multiple user names on the command line. Note that on GNU systems, options to `passwd(1)` may be specified after the user argument. As a result, this rule will also allow:

```
passwd username --expire
```

which may not be desirable.

```
bob      SPARC = (OP) ALL : SGI = (OP) ALL
```

The user `bob` may run anything on the SPARC and SGI machines as any user listed in the `OP` `Runas_Alias` (root and operator.)

```
jim      +biglab = ALL
```

The user `jim` may run any command on machines in the `biglab` netgroup. `sudo` knows that `?biglab?` is a netgroup due to the `?+?` prefix.

```
+secretaries ALL = PRINTING, /usr/bin/adduser, /usr/bin/rmuser
```

Users in the `secretaries` netgroup need to help manage the printers as well as add and remove users, so they are allowed to run those commands on all machines.

```
fred     ALL = (DB) NOPASSWD: ALL
```

The user `fred` can run commands as any user in the `DB` `Runas_Alias` (oracle or sybase) without giving a password.

```
john     ALPHA = /usr/bin/su [!-]*, !/usr/bin/su *root*
```

On the ALPHA machines, user `john` may su to anyone except root but he is not allowed to specify any options to the `su(1)` command.

```
jen      ALL, !SERVERS = ALL
```

The user jill may run any command on any machine except for those in the SERVERS Host_Alias (master, mail, www and ns).

```
jill    SERVERS = /usr/bin/, !SU, !SHELLS
```

For any machine in the SERVERS Host_Alias, jill may run any commands in the directory /usr/bin/ except for those commands belonging to the SU and SHELLS Cmnd_Aliases.

While not specifically mentioned in the rule, the commands in the PAGERS Cmnd_Alias all reside in /usr/bin and have the noexec option set.

```
steve   CSNETS = (operator) /usr/local/op_commands/
```

The user steve may run any command in the directory /usr/local/op_commands/ but only as user operator.

```
matt    valkyrie = KILL
```

On his personal workstation, valkyrie, matt needs to be able to kill hung processes.

```
WEBMASTERS    www = (www) ALL, (root) /usr/bin/su www
```

On the host www, any user in the WEBMASTERS User_Alias (will, wendy, and wim), may run any command as user www (which owns the web pages) or simply su(1) to www.

```
ALL      CDROM = NOPASSWD: /sbin/umount /CDROM,\n          /sbin/mount -o nosuid,nodev /dev/cd0a /CDROM
```

Any user may mount or unmount a CD-ROM on the machines in the CDROM Host_Alias (orion, perseus, hercules) without entering a password. This is a bit tedious for users to type, so it is a prime candidate for encapsulating in a shell script.

SECURITY NOTES

Limitations of the ! operator

It is generally not effective to subtract commands from ALL using the ! operator.

A user can trivially circumvent this by copying the desired command to a different name and then executing that. For example:

```
bill    ALL = ALL, !SU, !SHELLS
```

Doesn't really prevent bill from running the commands listed in SU or SHELLS since he can simply copy those commands to a different name, or use a shell escape from an editor or other program. Therefore, these kind of restrictions should be considered advisory at best (and reinforced by policy).

In general, if a user has sudo ALL there is nothing to prevent them from creating their own program that gives them a root shell (or making their own copy of a shell) regardless of any ! elements in the user specification.

Security implications of fast_glob

If the fast_glob option is in use, it is not possible to reliably negate commands where the path name includes globbing (aka wildcard) characters. This is because the C library's fnmatch(3) function cannot resolve relative paths. While this is typically only an inconvenience for rules that grant privileges, it can result in a security issue for rules that subtract or revoke privileges.

For example, given the following sudoers file entry:

```
john  ALL = /usr/bin/passwd [a-zA-Z0-9]*, /usr/bin/chsh [a-zA-Z0-9]*, \
      /usr/bin/chfn [a-zA-Z0-9]*, !/usr/bin/* root
```

User john can still run /usr/bin/passwd root if fast_glob is enabled by changing to /usr/bin and running ./passwd root instead.

Preventing shell escapes

Once sudo executes a program, that program is free to do whatever it pleases, including run other programs. This can be a security issue since it is not uncommon for a program to allow shell escapes, which lets a user bypass sudo's access control and logging. Common programs that permit shell escapes include shells (obviously), editors, paginators, mail and terminal programs.

There are two basic approaches to this problem:

restrict Avoid giving users access to commands that allow the user to run arbitrary commands. Many editors have a restricted mode where shell escapes are disabled, though sudoedit is a better solution to running editors via sudo.

Due to the large number of programs that offer shell escapes, restricting users to the set of programs that do not is often unworkable.

noexec Many systems that support shared libraries have the ability to override default library functions by pointing an environment variable (usually LD_PRELOAD) to an alternate shared library. On such systems, sudo's noexec functionality can be used to prevent a program run by sudo from executing any other programs. Note, however, that this applies only to native dynamically-linked executables. Statically-linked executables and foreign executables running under binary emulation are not affected.

The noexec feature is known to work on SunOS, Solaris, *BSD, Linux, IRIX, Tru64 UNIX, macOS, HP-UX 11.x and AIX 5.3 and above. It should be supported on most operating systems that support the LD_PRELOAD environment

variable. Check your operating system's manual pages for the dynamic linker (usually `ld.so`, `ld.so.1`, `dylld`, `dld.sl`, `rld`, or `loader`) to see if `LD_PRELOAD` is supported.

On Solaris 10 and higher, `noexec` uses Solaris privileges instead of the `LD_PRELOAD` environment variable.

To enable `noexec` for a command, use the `NOEXEC` tag as documented in the User Specification section above. Here is that example again:

```
aaron shanty = NOEXEC: /usr/bin/more, /usr/bin/vi
```

This allows user `aaron` to run `/usr/bin/more` and `/usr/bin/vi` with `noexec` enabled. This will prevent those two commands from executing other commands (such as a shell). If you are unsure whether or not your system is capable of supporting `noexec` you can always just try it out and check whether shell escapes work when `noexec` is enabled.

Note that restricting shell escapes is not a panacea. Programs running as root are still capable of many potentially hazardous operations (such as changing or overwriting files) that could lead to unintended privilege escalation. In the specific case of an editor, a safer approach is to give the user permission to run `sudoedit` (see below).

Secure editing

The `sudoers` plugin includes `sudoedit` support which allows users to securely edit files with the editor of their choice. As `sudoedit` is a built-in command, it must be specified in the `sudoers` file without a leading path. However, it may take command line arguments just as a normal command does. Wildcards used in `sudoedit` command line arguments are expected to be path names, so a forward slash (`/?/`) will not be matched by a wildcard.

Unlike other `sudo` commands, the editor is run with the permissions of the invoking user and with the environment unmodified. More information may be found in the description of the `-e` option in `sudo(8)`.

For example, to allow user `operator` to edit the `?message of the day?` file:

```
operator    sudoedit /etc/motd
```

The `operator` user then runs `sudoedit` as follows:

```
$ sudoedit /etc/motd
```

The editor will run as the `operator` user, not root, on a temporary copy of `/etc/motd`.

After the file has been edited, `/etc/motd` will be updated with the contents of the temporary copy.

Users should never be granted `sudoedit` permission to edit a file that resides in a directory the user has write access to, either directly or via a wildcard. If the user has write access to the directory it is possible to replace the legitimate file with a link to another file, allowing the editing of arbitrary files. To prevent this, starting with version 1.8.16, symbolic links will not be followed in writable directories and `sudoedit` will refuse to edit a file located in a writable directory unless the `sudoedit_checkdir` option has been disabled or the invoking user is root. Additionally, in version 1.8.15 and higher, `sudoedit` will refuse to open a symbolic link unless either the `sudoedit_follow` option is enabled or the `sudoedit` command is prefixed with the `FOLLOW` tag in the `sudoers` file.

Time stamp file checks

`sudoers` will check the ownership of its time stamp directory (`/run/sudo/ts` by default) and ignore the directory's contents if it is not owned by root or if it is writable by a user other than root. Older versions of `sudo` stored time stamp files in `/tmp`; this is no longer recommended as it may be possible for a user to create the time stamp themselves on systems that allow unprivileged users to change the ownership of files they create.

While the time stamp directory should be cleared at reboot time, not all systems contain a `/run` or `/var/run` directory. To avoid potential problems, `sudoers` will ignore time stamp files that date from before the machine booted on systems where the boot time is available.

Some systems with graphical desktop environments allow unprivileged users to change the system clock. Since `sudoers` relies on the system clock for time stamp validation, it may be possible on such systems for a user to run `sudo` for longer than `timestamp_timeout` by setting the clock back. To combat this, `sudoers` uses a monotonic clock (which never moves backwards) for its time stamps if the system supports it.

`sudoers` will not honor time stamps set far in the future. Time stamps with a date greater than `current_time + 2 * TIMEOUT` will be ignored and `sudoers` will log and complain.

If the `timestamp_type` option is set to `?tty?`, the time stamp record includes the de?

vice number of the terminal the user authenticated with. This provides per-terminal granularity but time stamp records may still outlive the user's session.

Unless the `timestamp_type` option is set to `?global?`, the time stamp record also includes the session ID of the process that last authenticated. This prevents processes in different terminal sessions from using the same time stamp record. On systems where a process's start time can be queried, the start time of the session leader is recorded in the time stamp record. If no terminal is present or the `timestamp_type` option is set to `?ppid?`, the start time of the parent process is used instead. In most cases this will prevent a time stamp record from being re-used without the user entering a password when logging out and back in again.

DEBUGGING

Versions 1.8.4 and higher of the sudoers plugin support a flexible debugging framework that can help track down what the plugin is doing internally if there is a problem. This can be configured in the `sudo.conf(5)` file.

The sudoers plugin uses the same debug flag format as the sudo front-end: `subsystem@priority`.

The priorities used by sudoers, in order of decreasing severity, are: `crit`, `err`, `warn`, `notice`, `diag`, `info`, `trace` and `debug`. Each priority, when specified, also includes all priorities higher than it. For example, a priority of `notice` would include debug messages logged at `notice` and higher.

The following subsystems are used by the sudoers plugin:

`alias` User_Alias, Runas_Alias, Host_Alias and Cmnd_Alias processing

`all` matches every subsystem

`audit` BSM and Linux audit code

`auth` user authentication

`defaults` sudoers file Defaults settings

`env` environment handling

`ldap` LDAP-based sudoers

`logging` logging support

`match` matching of users, groups, hosts and netgroups in the sudoers file

`netif` network interface handling

`nss` network service switch handling in sudoers

`parser` sudoers file parsing

perms permission setting

plugin The equivalent of main for the plugin.

pty pseudo-terminal related code

rbtree redblack tree internals

sssd SSSD-based sudoers

util utility functions

For example:

Debug sudo /var/log/sudo_debug match@info,nss@info

For more information, see the sudo.conf(5) manual.

SEE ALSO

ssh(1), su(1), fnmatch(3), glob(3), mktemp(3), strftime(3), sudo.conf(5),

sudo_plugin(5), sudoers.ldap(5), sudoers_timestamp(5), sudo(8), visudo(8)

AUTHORS

Many people have worked on sudo over the years; this version consists of code written primarily by:

Todd C. Miller

See the CONTRIBUTORS file in the sudo distribution (<https://www.sudo.ws/contributors.html>) for an exhaustive list of people who have contributed to sudo.

CAVEATS

The sudoers file should always be edited by the visudo command which locks the file and does grammatical checking. It is imperative that the sudoers file be free of syntax errors since sudo will not run with a syntactically incorrect sudoers file.

When using netgroups of machines (as opposed to users), if you store fully qualified host name in the netgroup (as is usually the case), you either need to have the machine's host name be fully qualified as returned by the hostname command or use the fqdn option in sudoers.

BUGS

If you feel you have found a bug in sudo, please submit a bug report at <https://bugzilla.sudo.ws/>

SUPPORT

Limited free support is available via the sudo-users mailing list, see <https://www.sudo.ws/mailman/listinfo/sudo-users> to subscribe or search the archives.

DISCLAIMER

sudo is provided ?AS IS? and any express or implied warranties, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose are disclaimed. See the LICENSE file distributed with sudo or <https://www.sudo.ws/license.html> for complete details.

Sudo 1.8.31

December 9, 2019

Sudo 1.8.31