



*Full credit is given to the above companies including the OS that this PDF file was generated!*

## **Red Hat Enterprise Linux Release 9.2 Manual Pages on 'CMS\_set1\_eContentType.3ossl' command**

```
$ man CMS_set1_eContentType.3ossl
```

```
CMS_GET0_TYPE(3ossl)      OpenSSL      CMS_GET0_TYPE(3ossl)
```

### NAME

CMS\_get0\_type, CMS\_set1\_eContentType, CMS\_get0\_eContentType,  
CMS\_get0\_content - get and set CMS content types and content

### SYNOPSIS

```
#include <openssl/cms.h>
```

```
const ASN1_OBJECT *CMS_get0_type(const CMS_ContentInfo *cms);  
int CMS_set1_eContentType(CMS_ContentInfo *cms, const ASN1_OBJECT *oid);  
const ASN1_OBJECT *CMS_get0_eContentType(CMS_ContentInfo *cms);  
ASN1_OCTET_STRING **CMS_get0_content(CMS_ContentInfo *cms);
```

### DESCRIPTION

CMS\_get0\_type() returns the content type of a CMS\_ContentInfo structure as an ASN1\_OBJECT pointer. An application can then decide how to process the CMS\_ContentInfo structure based on this value.

CMS\_set1\_eContentType() sets the embedded content type of a CMS\_ContentInfo structure. It should be called with CMS functions (such as CMS\_sign(3), CMS\_encrypt(3)) with the CMS\_PARTIAL flag and before the structure is finalised, otherwise the results are undefined.

ASN1\_OBJECT \*CMS\_get0\_eContentType() returns a pointer to the embedded content type.

CMS\_get0\_content() returns a pointer to the ASN1\_OCTET\_STRING pointer containing the embedded content.

## NOTES

As the 0 implies CMS\_get0\_type(), CMS\_get0\_eContentType() and CMS\_get0\_content() return internal pointers which should not be freed up. CMS\_set1\_eContentType() copies the supplied OID and it should be freed up after use.

The ASN1\_OBJECT values returned can be converted to an integer NID value using OBJ\_obj2nid(). For the currently supported content types the following values are returned:

NID\_pkcs7\_data

NID\_pkcs7\_signed

NID\_pkcs7\_digest

NID\_id\_smime\_ct\_compressedData:

NID\_pkcs7\_encrypted

NID\_pkcs7\_enveloped

The return value of CMS\_get0\_content() is a pointer to the ASN1\_OCTET\_STRING content pointer. That means that for example:

```
ASN1_OCTET_STRING **pconf = CMS_get0_content/cms);
```

\*pconf could be NULL if there is no embedded content. Applications can access, modify or create the embedded content in a CMS\_ContentInfo structure using this function. Applications usually will not need to modify the embedded content as it is normally set by higher level

functions.

## RETURN VALUES

`CMS_get0_type()` and `CMS_get0_eContentType()` return an `ASN1_OBJECT` structure.

`CMS_set1_eContentType()` returns 1 for success or 0 if an error occurred. The error can be obtained from `ERR_get_error(3)`.

## SEE ALSO

`ERR_get_error(3)`

## COPYRIGHT

Copyright 2008-2016 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file `LICENSE` in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7                      2023-07-13                      CMS\_GET0\_TYPE(3openssl)