



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'SSL_CTX_get_info_callback.3ossl' command

`$ man SSL_CTX_get_info_callback.3ossl`

`SSL_CTX_SET_INFO_CALLBACK(3ossl) OpenSSL SSL_CTX_SET_INFO_CALLBACK(3ossl)`

NAME

SSL_CTX_set_info_callback, SSL_CTX_get_info_callback,
SSL_set_info_callback, SSL_get_info_callback - handle information
callback for SSL connections

SYNOPSIS

```
#include <openssl/ssl.h>

void SSL_CTX_set_info_callback(SSL_CTX *ctx, void (*callback)());
void (*SSL_CTX_get_info_callback(const SSL_CTX *ctx))();

void SSL_set_info_callback(SSL *ssl, void (*callback)());
void (*SSL_get_info_callback(const SSL *ssl))();
```

DESCRIPTION

SSL_CTX_set_info_callback() sets the callback function, that can be used to obtain state information for SSL objects created from ctx during connection setup and use. The setting for ctx is overridden from the setting for a specific SSL object, if specified. When callback is NULL, no callback function is used.

SSL_set_info_callback() sets the callback function, that can be used to obtain state information for ssl during connection setup and use. When callback is NULL, the callback setting currently valid for ctx is used.

SSL_CTX_get_info_callback() returns a pointer to the currently set information callback function for ctx.

SSL_get_info_callback() returns a pointer to the currently set information callback function for ssl.

NOTES

When setting up a connection and during use, it is possible to obtain state information from the SSL/TLS engine. When set, an information callback function is called whenever a significant event occurs such as: the state changes, an alert appears, or an error occurs.

The callback function is called as callback(SSL *ssl, int where, int ret). The where argument specifies information about where (in which context) the callback function was called. If ret is 0, an error condition occurred. If an alert is handled, SSL_CB_ALERT is set and ret specifies the alert information.

where is a bit-mask made up of the following bits:

SSL_CB_LOOP

Callback has been called to indicate state change or some other significant state machine event. This may mean that the callback gets invoked more than once per state in some situations.

SSL_CB_EXIT

Callback has been called to indicate exit of a handshake function. This will happen after the end of a handshake, but may happen at other times too such as on error or when IO might otherwise block

and nonblocking is being used.

SSL_CB_READ

Callback has been called during read operation.

SSL_CB_WRITE

Callback has been called during write operation.

SSL_CB_ALERT

Callback has been called due to an alert being sent or received.

| | |
|------------------------|------------------------------|
| SSL_CB_READ_ALERT | (SSL_CB_ALERT SSL_CB_READ) |
| SSL_CB_WRITE_ALERT | (SSL_CB_ALERT SSL_CB_WRITE) |
| SSL_CB_ACCEPT_LOOP | (SSL_ST_ACCEPT SSL_CB_LOOP) |
| SSL_CB_ACCEPT_EXIT | (SSL_ST_ACCEPT SSL_CB_EXIT) |
| SSL_CB_CONNECT_LOOP | (SSL_ST_CONNECT SSL_CB_LOOP) |
| SSL_CB_CONNECT_EXIT | (SSL_ST_CONNECT SSL_CB_EXIT) |
| SSL_CB_HANDSHAKE_START | |

Callback has been called because a new handshake is started. It also occurs when resuming a handshake following a pause to handle early data.

SSL_CB_HANDSHAKE_DONE

Callback has been called because a handshake is finished. It also occurs if the handshake is paused to allow the exchange of early data.

The current state information can be obtained using the `SSL_state_string(3)` family of functions.

The ret information can be evaluated using the `SSL_alert_type_string(3)` family of functions.

RETURN VALUES

SSL_set_info_callback() does not provide diagnostic information.

SSL_get_info_callback() returns the current setting.

EXAMPLES

The following example callback function prints state strings, information about alerts being handled and error messages to the bio_err BIO.

```
void apps_ssl_info_callback(SSL *s, int where, int ret)
{
    const char *str;
    int w = where & ~SSL_ST_MASK;

    if (w & SSL_ST_CONNECT)
        str = "SSL_connect";
    else if (w & SSL_ST_ACCEPT)
        str = "SSL_accept";
    else
        str = "undefined";

    if (where & SSL_CB_LOOP) {
        BIO_printf(bio_err, "%s:%s\n", str, SSL_state_string_long(s));
    } else if (where & SSL_CB_ALERT) {
        str = (where & SSL_CB_READ) ? "read" : "write";
        BIO_printf(bio_err, "SSL3 alert %s:%s:%s\n", str,
            SSL_alert_type_string_long(ret),
            SSL_alert_desc_string_long(ret));
    } else if (where & SSL_CB_EXIT) {
        if (ret == 0) {
            BIO_printf(bio_err, "%s:failed in %s\n",
                str, SSL_state_string_long(s));
        }
    }
}
```

```
    } else if (ret < 0) {  
        BIO_printf(bio_err, "%s:error in %s\n",  
            str, SSL_state_string_long(s));  
    }  
}  
}
```

SEE ALSO

ssl(7), SSL_state_string(3), SSL_alert_type_string(3)

COPYRIGHT

Copyright 2001-2020 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7 2023-07-13 SSL_CTX_SET_INFO_CALLBACK(3ossl)