



Red Hat Enterprise Linux Release 9.2 Manual Pages on 'SSL_CTX_set_async_callback.3ossl' command

\$ man SSL_CTX_set_async_callback.3ossl

SSL_CTX_set_async_callback(3ossl) OpenSSL SSL_CTX_set_async_callback(3ossl)

NAME

SSL_CTX_set_async_callback, SSL_CTX_set_async_callback_arg,
SSL_set_async_callback, SSL_set_async_callback_arg,
SSL_get_async_status, SSL_async_callback_fn - manage asynchronous
operations

SYNOPSIS

```
#include <openssl/ssl.h>

typedef int (*SSL_async_callback_fn)(SSL *s, void *arg);

int SSL_CTX_set_async_callback(SSL_CTX *ctx, SSL_async_callback_fn callback);

int SSL_CTX_set_async_callback_arg(SSL_CTX *ctx, void *arg);

int SSL_set_async_callback(SSL *s, SSL_async_callback_fn callback);

int SSL_set_async_callback_arg(SSL *s, void *arg);

int SSL_get_async_status(SSL *s, int *status);
```

DESCRIPTION

SSL_CTX_set_async_callback() sets an asynchronous callback function.
All SSL objects generated based on this SSL_CTX will get this callback.
If an engine supports the callback mechanism, it will be automatically
called if SSL_MODE_ASYNC has been set and an asynchronous capable
engine completes a cryptography operation to notify the application to
resume the paused work flow.
SSL_CTX_set_async_callback_arg() sets the callback argument.
SSL_set_async_callback() allows an application to set a callback in an

asynchronous SSL object, so that when an engine completes a cryptography operation, the callback will be called to notify the application to resume the paused work flow.

`SSL_set_async_callback_arg()` sets an argument for the SSL object when the above callback is called.

`SSL_get_async_status()` returns the engine status. This function facilitates the communication from the engine to the application.

During an SSL session, cryptographic operations are dispatched to an engine. The engine status is very useful for an application to know if the operation has been successfully dispatched. If the engine does not support this additional callback method, `ASYNC_STATUS_UNSUPPORTED` will be returned. See `ASYNC_WAIT_CTX_set_status()` for a description of all of the status values.

An example of the above functions would be the following:

1. Application sets the async callback and callback data on an SSL connection by calling `SSL_set_async_callback()`.
2. Application sets `SSL_MODE_ASYNC` and makes an asynchronous SSL call
3. OpenSSL submits the asynchronous request to the engine. If a retry occurs at this point then the status within the `ASYNC_WAIT_CTX` would be set and the async callback function would be called (goto Step 7).
4. The OpenSSL engine pauses the current job and returns, so that the application can continue processing other connections.
5. At a future point in time (probably via a polling mechanism or via an interrupt) the engine will become aware that the asynchronous request has finished processing.
6. The engine will call the application's callback passing the callback data as a parameter.
7. The callback function should then run. Note: it is a requirement that the callback function is small and nonblocking as it will be run in the context of a polling mechanism or an interrupt.
8. It is the application's responsibility via the callback function to schedule recalling the OpenSSL asynchronous function and to

continue processing.

9. The callback function has the option to check the status returned via `SSL_get_async_status()` to determine whether a retry happened instead of the request being submitted, allowing different processing if required.

RETURN VALUES

`SSL_CTX_set_async_callback()`, `SSL_set_async_callback()`,
`SSL_CTX_set_async_callback_arg()`, `SSL_CTX_set_async_callback_arg()` and
`SSL_get_async_status()` return 1 on success or 0 on error.

SEE ALSO

`ssl(7)`

HISTORY

`SSL_CTX_set_async_callback()`, `SSL_CTX_set_async_callback_arg()`,
`SSL_set_async_callback()`, `SSL_set_async_callback_arg()` and
`SSL_get_async_status()` were first added to OpenSSL 3.0.

COPYRIGHT

Copyright 2019-2021 The OpenSSL Project Authors. All Rights Reserved.
Licensed under the Apache License 2.0 (the "License"). You may not use
this file except in compliance with the License. You can obtain a copy
in the file LICENSE in the source distribution or at
<<https://www.openssl.org/source/license.html>>.

3.0.7 2023-07-13 `SSL_SET_ASYNC_CALLBACK(3ossl)`