



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'SSL_SESSION_dup.3ossl' command

\$ man SSL_SESSION_dup.3ossl

SSL_SESSION_FREE(3ossl) OpenSSL SSL_SESSION_FREE(3ossl)

NAME

SSL_SESSION_new, SSL_SESSION_dup, SSL_SESSION_up_ref, SSL_SESSION_free
- create, free and manage SSL_SESSION structures

SYNOPSIS

```
#include <openssl/ssl.h>

SSL_SESSION *SSL_SESSION_new(void);

SSL_SESSION *SSL_SESSION_dup(const SSL_SESSION *src);

int SSL_SESSION_up_ref(SSL_SESSION *ses);

void SSL_SESSION_free(SSL_SESSION *session);
```

DESCRIPTION

SSL_SESSION_new() creates a new SSL_SESSION structure and returns a pointer to it.

SSL_SESSION_dup() copies the contents of the SSL_SESSION structure in src and returns a pointer to it.

SSL_SESSION_up_ref() increments the reference count on the given SSL_SESSION structure.

SSL_SESSION_free() decrements the reference count of session and removes the SSL_SESSION structure pointed to by session and frees up the allocated memory, if the reference count has reached 0. If session is NULL nothing is done.

NOTES

SSL_SESSION objects are allocated, when a TLS/SSL handshake operation

is successfully completed. Depending on the settings, see `SSL_CTX_set_session_cache_mode(3)`, the `SSL_SESSION` objects are internally referenced by the `SSL_CTX` and linked into its session cache. `SSL` objects may be using the `SSL_SESSION` object; as a session may be reused, several `SSL` objects may be using one `SSL_SESSION` object at the same time. It is therefore crucial to keep the reference count (usage information) correct and not delete a `SSL_SESSION` object that is still used, as this may lead to program failures due to dangling pointers. These failures may also appear delayed, e.g. when an `SSL_SESSION` object was completely freed as the reference count incorrectly became 0, but it is still referenced in the internal session cache and the cache list is processed during a `SSL_CTX_flush_sessions(3)` operation. `SSL_SESSION_free()` must only be called for `SSL_SESSION` objects, for which the reference count was explicitly incremented (e.g. by calling `SSL_get1_session()`, see `SSL_get_session(3)`) or when the `SSL_SESSION` object was generated outside a TLS handshake operation, e.g. by using `d2i_SSL_SESSION(3)`. It must not be called on other `SSL_SESSION` objects, as this would cause incorrect reference counts and therefore program failures.

RETURN VALUES

`SSL_SESSION_new` returns a pointer to the newly allocated `SSL_SESSION` structure or `NULL` on error.

`SSL_SESSION_up_ref` returns 1 on success or 0 on error.

SEE ALSO

`ssl(7)`, `SSL_get_session(3)`, `SSL_CTX_set_session_cache_mode(3)`,
`SSL_CTX_flush_sessions(3)`, `d2i_SSL_SESSION(3)`

HISTORY

The `SSL_SESSION_dup()` function was added in OpenSSL 1.1.1.

COPYRIGHT

Copyright 2000-2016 The OpenSSL Project Authors. All Rights Reserved.
Licensed under the Apache License 2.0 (the "License"). You may not use
this file except in compliance with the License. You can obtain a copy
in the file `LICENSE` in the source distribution or at

<<https://www.openssl.org/source/license.html>>.

3.0.7

2023-07-13

SSL_SESSION_FREE(3ossl)