



## **Red Hat Enterprise Linux Release 9.2 Manual Pages on 'SSL\_get\_ssl\_method.3ossl' command**

**\$ man SSL\_get\_ssl\_method.3ossl**

SSL\_CTX\_SET\_SSL\_VERSION(3ossl) OpenSSL SSL\_CTX\_SET\_SSL\_VERSION(3ossl)

### NAME

SSL\_CTX\_set\_ssl\_version, SSL\_CTX\_get\_ssl\_method, SSL\_set\_ssl\_method,  
SSL\_get\_ssl\_method - choose a new TLS/SSL method

### SYNOPSIS

```
#include <openssl/ssl.h>

int SSL_CTX_set_ssl_version(SSL_CTX *ctx, const SSL_METHOD *method);

const SSL_METHOD *SSL_CTX_get_ssl_method(const SSL_CTX *ctx);

int SSL_set_ssl_method(SSL *s, const SSL_METHOD *method);

const SSL_METHOD *SSL_get_ssl_method(const SSL *ssl);
```

### DESCRIPTION

SSL\_CTX\_set\_ssl\_version() sets a new default TLS/SSL method for SSL objects newly created from this ctx. Most of the configuration attached to the SSL\_CTX object is retained, with the exception of the configured TLS ciphers, which are reset to the default values. SSL objects already created from this SSL\_CTX with SSL\_new(3) are not affected, except when SSL\_clear(3) is being called, as described below.

SSL\_CTX\_get\_ssl\_method() returns the SSL\_METHOD which was used to construct the SSL\_CTX.

SSL\_set\_ssl\_method() sets a new TLS/SSL method for a particular ssl object. It may be reset, when SSL\_clear() is called.

SSL\_get\_ssl\_method() returns a pointer to the TLS/SSL method set in ssl.

## NOTES

The available method choices are described in `SSL_CTX_new(3)`.

When `SSL_clear(3)` is called and no session is connected to an SSL object, the method of the SSL object is reset to the method currently set in the corresponding `SSL_CTX` object.

`SSL_CTX_set_version()` has unusual semantics and no clear use case; it would usually be preferable to create a new `SSL_CTX` object than to try to reuse an existing one in this fashion. Its usage is considered deprecated.

## RETURN VALUES

The following return values can occur for `SSL_CTX_set_ssl_version()` and `SSL_set_ssl_method()`:

0 The new choice failed, check the error stack to find out the reason.

1 The operation succeeded.

`SSL_CTX_get_ssl_method()` and `SSL_get_ssl_method()` always return non-NULL pointers.

## SEE ALSO

`SSL_CTX_new(3)`, `SSL_new(3)`, `SSL_clear(3)`, `ssl(7)`,

`SSL_set_connect_state(3)`

## HISTORY

`SSL_CTX_set_ssl_version()` was deprecated in OpenSSL 3.0.

## COPYRIGHT

Copyright 2000-2022 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use

this file except in compliance with the License. You can obtain a copy

in the file `LICENSE` in the source distribution or at

[<https://www.openssl.org/source/license.html>](https://www.openssl.org/source/license.html).

3.0.7                    2023-07-13    `SSL_CTX_SET_SSL_VERSION(3ossl)`