



*Full credit is given to the above companies including the OS that this PDF file was generated!*

## **Red Hat Enterprise Linux Release 9.2 Manual Pages on 'SSL\_is\_init\_finished.3ossl' command**

**\$ man SSL\_is\_init\_finished.3ossl**

SSL\_IN\_INIT(3ossl)            OpenSSL            SSL\_IN\_INIT(3ossl)

### NAME

SSL\_in\_before, SSL\_in\_init, SSL\_is\_init\_finished, SSL\_in\_connect\_init,  
SSL\_in\_accept\_init, SSL\_get\_state - retrieve information about the  
handshake state machine

### SYNOPSIS

```
#include <openssl/ssl.h>
```

```
int SSL_in_init(const SSL *s);
```

```
int SSL_in_before(const SSL *s);
```

```
int SSL_is_init_finished(const SSL *s);
```

```
int SSL_in_connect_init(SSL *s);
```

```
int SSL_in_accept_init(SSL *s);
```

```
OSSL_HANDSHAKE_STATE SSL_get_state(const SSL *ssl);
```

### DESCRIPTION

SSL\_in\_init() returns 1 if the SSL/TLS state machine is currently processing or awaiting handshake messages, or 0 otherwise.

SSL\_in\_before() returns 1 if no SSL/TLS handshake has yet been initiated, or 0 otherwise.

SSL\_is\_init\_finished() returns 1 if the SSL/TLS connection is in a state where fully protected application data can be transferred or 0 otherwise.

Note that in some circumstances (such as when early data is being transferred) SSL\_in\_init(), SSL\_in\_before() and SSL\_is\_init\_finished() can all return 0.

SSL\_in\_connect\_init() returns 1 if s is acting as a client and SSL\_in\_init() would return 1, or 0 otherwise.

SSL\_in\_accept\_init() returns 1 if s is acting as a server and SSL\_in\_init() would return 1, or 0 otherwise.

SSL\_in\_connect\_init() and SSL\_in\_accept\_init() are implemented as macros.

SSL\_get\_state() returns a value indicating the current state of the handshake state machine. OSSL\_HANDSHAKE\_STATE is an enumerated type where each value indicates a discrete state machine state. Note that future versions of OpenSSL may define more states so applications should expect to receive unrecognised state values. The naming format is made up of a number of elements as follows:

protocol\_ST\_role\_message

protocol is one of TLS or DTLS. DTLS is used where a state is specific to the DTLS protocol. Otherwise TLS is used.

role is one of CR, CW, SR or SW to indicate "client reading", "client

writing", "server reading" or "server writing" respectively.

message is the name of a handshake message that is being or has been sent, or is being or has been processed.

Additionally there are some special states that do not conform to the above format. These are:

#### TLS\_ST\_BEFORE

No handshake messages have yet been sent or received.

#### TLS\_ST\_OK

Handshake message sending/processing has completed.

#### TLS\_ST\_EARLY\_DATA

Early data is being processed

#### TLS\_ST\_PENDING\_EARLY\_DATA\_END

Awaiting the end of early data processing

#### RETURN VALUES

SSL\_in\_init(), SSL\_in\_before(), SSL\_is\_init\_finished(),  
SSL\_in\_connect\_init() and SSL\_in\_accept\_init() return values as indicated above.

SSL\_get\_state() returns the current handshake state.

#### SEE ALSO

ssl(7), SSL\_read\_early\_data(3)

#### COPYRIGHT

Copyright 2017-2018 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7                      2023-07-13                      SSL\_IN\_INIT(3ossl)