



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'EVP_PKEY_get_utf8_string_param.3ossl'

\$ man EVP_PKEY_get_utf8_string_param.3ossl

EVP_PKEY_GETTABLE_PARAMS(3ossl) OpenSSL EVP_PKEY_GETTABLE_PARAMS(3ossl)

NAME

EVP_PKEY_gettable_params, EVP_PKEY_get_params, EVP_PKEY_get_int_param,
EVP_PKEY_get_size_t_param, EVP_PKEY_get_bn_param,
EVP_PKEY_get_utf8_string_param, EVP_PKEY_get_octet_string_param -
retrieve key parameters from a key

SYNOPSIS

```
#include <openssl/evp.h>
```

```
const OSSL_PARAM *EVP_PKEY_gettable_params(EVP_PKEY *pkey);
```

```
int EVP_PKEY_get_params(const EVP_PKEY *pkey, OSSL_PARAM params[]);
```

```
int EVP_PKEY_get_int_param(const EVP_PKEY *pkey, const char *key_name,  
                           int *out);
```

```
int EVP_PKEY_get_size_t_param(const EVP_PKEY *pkey, const char *key_name,  
                              size_t *out);
```

```
int EVP_PKEY_get_bn_param(const EVP_PKEY *pkey, const char *key_name,
```

```

        BIGNUM **bn);

int EVP_PKEY_get_utf8_string_param(const EVP_PKEY *pkey, const char *key_name,
        char *str, size_t max_buf_sz,
        size_t *out_len);

int EVP_PKEY_get_octet_string_param(const EVP_PKEY *pkey, const char *key_name,
        unsigned char *buf, size_t max_buf_sz,
        size_t *out_len);

```

DESCRIPTION

`EVP_PKEY_get_params()` retrieves parameters from the key `pkey`, according to the contents of `params`. See `OSSL_PARAM(3)` for information about parameters.

`EVP_PKEY_gettable_params()` returns a constant list of `params` indicating the names and types of key parameters that can be retrieved. See `OSSL_PARAM(3)` for information about parameters.

An `OSSL_PARAM` of type `OSSL_PARAM_INTEGER` or `OSSL_PARAM_UNSIGNED_INTEGER` is of arbitrary length. Such a parameter can be obtained using any of the functions `EVP_PKEY_get_int_param()`, `EVP_PKEY_get_size_t_param()` or `EVP_PKEY_get_bn_param()`. Attempting to obtain an integer value that does not fit into a native C `int` type will cause `EVP_PKEY_get_int_param()` to fail. Similarly attempting to obtain an integer value that is negative or does not fit into a native C `size_t` type using `EVP_PKEY_get_size_t_param()` will also fail.

`EVP_PKEY_get_int_param()` retrieves a key `pkey` integer value `*out` associated with a name of `key_name` if it fits into "int" type. For parameters that do not fit into "int" use `EVP_PKEY_get_bn_param()`.

`EVP_PKEY_get_size_t_param()` retrieves a key `pkey` `size_t` value `*out` associated with a name of `key_name` if it fits into "size_t" type. For parameters that do not fit into "size_t" use `EVP_PKEY_get_bn_param()`.

EVP_PKEY_get_bn_param() retrieves a key pkey BIGNUM value **bn associated with a name of key_name. If *bn is NULL then the BIGNUM is allocated by the method.

EVP_PKEY_get_utf8_string_param() get a key pkey UTF8 string value into a buffer str of maximum size max_buf_sz associated with a name of key_name. The maximum size must be large enough to accomodate the string value including a terminating NUL byte, or this function will fail. If out_len is not NULL, *out_len is set to the length of the string not including the terminating NUL byte. The required buffer size not including the terminating NUL byte can be obtained from *out_len by calling the function with str set to NULL.

EVP_PKEY_get_octet_string_param() get a key pkey's octet string value into a buffer buf of maximum size max_buf_sz associated with a name of key_name. If out_len is not NULL, *out_len is set to the length of the contents. The required buffer size can be obtained from *out_len by calling the function with buf set to NULL.

NOTES

These functions only work for EVP_PKEYs that contain a provider side key.

RETURN VALUES

EVP_PKEY_gettable_params() returns NULL on error or if it is not supported.

All other methods return 1 if a value associated with the key's key_name was successfully returned, or 0 if there was an error. An error may be returned by methods EVP_PKEY_get_utf8_string_param() and EVP_PKEY_get_octet_string_param() if max_buf_sz is not big enough to hold the value. If out_len is not NULL, *out_len will be assigned the

required buffer size to hold the value.

EXAMPLES

```
#include <openssl/evp.h>

char curve_name[64];
unsigned char pub[256];
BIGNUM *bn_priv = NULL;

/*
 * NB: assumes 'key' is set up before the next step. In this example the key
 * is an EC key.
 */

if (!EVP_PKEY_get_utf8_string_param(key, OSSL_PKEY_PARAM_GROUP_NAME,
                                     curve_name, sizeof(curve_name), &len)) {
    /* Error */
}

if (!EVP_PKEY_get_octet_string_param(key, OSSL_PKEY_PARAM_PUB_KEY,
                                     pub, sizeof(pub), &len)) {
    /* Error */
}

if (!EVP_PKEY_get_bn_param(key, OSSL_PKEY_PARAM_PRIV_KEY, &bn_priv)) {
    /* Error */
}

BN_clear_free(bn_priv);
```

SEE ALSO

[EVP_PKEY_CTX_new\(3\)](#), [provider-keymgmt\(7\)](#), [OSSL_PARAM\(3\)](#)

HISTORY

These functions were added in OpenSSL 3.0.

COPYRIGHT

Copyright 2020-2022 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7 2023-07-13 EVP_PKEY_GETTABLE_PARAMS(3ossl)