



Linux Ubuntu 26.04 Manual Pages on command 'adjtimex.2'

\$ man adjtimex.2

adjtimex(2) System Calls Manual adjtimex(2)

NAME

adjtimex, clock_adjtime, ntp_adjtime - tune kernel clock

LIBRARY

Standard C library (libc, -lc)

SYNOPSIS

```
#include <sys/timex.h>

int adjtimex(struct timex *buf);

int clock_adjtime(clockid_t clk_id, struct timex *buf);

int ntp_adjtime(struct timex *buf);
```

DESCRIPTION

Linux uses David L. Mills' clock adjustment algorithm (see RFC 5905). The system call adjtimex() reads and optionally sets adjustment parameters for this algorithm. It takes a pointer to a timex structure, updates kernel parameters from (selected) field values, and returns the same structure updated with the current kernel values. This structure is declared as follows:

```
struct timex {
    int modes; /* Mode selector */

    long offset; /* Time offset; nanoseconds, if STA_NANO
                 status flag is set, otherwise
                 microseconds */

    long freq; /* Frequency offset; see NOTES for units */

    long maxerror; /* Maximum error (microseconds) */
```

```

long esterror; /* Estimated error (microseconds) */

int status; /* Clock command/status */

long constant; /* PLL (phase-locked loop) time constant */

long precision; /* Clock precision

                (microseconds, read-only) */

long tolerance; /* Clock frequency tolerance (read-only);

                see NOTES for units */

struct timeval time;

/* Current time (read-only, except for

   ADJ_SETOFFSET); upon return, time.tv_usec

   contains nanoseconds, if STA_NANO status

   flag is set, otherwise microseconds */

long tick; /* Microseconds between clock ticks */

long ppsfreq; /* PPS (pulse per second) frequency

              (read-only); see NOTES for units */

long jitter; /* PPS jitter (read-only); nanoseconds, if

             STA_NANO status flag is set, otherwise

             microseconds */

int shift; /* PPS interval duration

           (seconds, read-only) */

long stabil; /* PPS stability (read-only);

            see NOTES for units */

long jitcnt; /* PPS count of jitter limit exceeded

            events (read-only) */

long calcnt; /* PPS count of calibration intervals

            (read-only) */

long errcnt; /* PPS count of calibration errors

            (read-only) */

long stbcnt; /* PPS count of stability limit exceeded

            events (read-only) */

int tai; /* TAI offset, as set by previous ADJ_TAI

         operation (seconds, read-only,

         since Linux 2.6.26) */

```

```
/* Further padding bytes to allow for future expansion */
```

```
};
```

The `modes` field determines which parameters, if any, to set. (As described later in this page, the constants used for `ntp_adjtime()` are equivalent but differently named.) It is a bit mask containing a bitwise OR combination of zero or more of the following bits:

ADJ_OFFSET

Set time offset from `buf.offset`. Since Linux 2.6.26, the supplied value is clamped to the range (-0.5s, +0.5s). In older kernels, an `EINVAL` error occurs if the supplied value is out of range.

ADJ_FREQUENCY

Set frequency offset from `buf.freq`. Since Linux 2.6.26, the supplied value is clamped to the range (-32768000, +32768000). In older kernels, an `EINVAL` error occurs if the supplied value is out of range.

ADJ_MAXERROR

Set maximum time error from `buf.maxerror`.

ADJ_ESTERROR

Set estimated time error from `buf.terror`.

ADJ_STATUS

Set clock status bits from `buf.status`. A description of these bits is provided below.

ADJ_TIMECONST

Set PLL time constant from `buf.constant`. If the `STA_NANO` status flag (see below) is clear, the kernel adds 4 to this value.

ADJ_SETOFFSET (since Linux 2.6.39)

Add `buf.time` to the current time. If `buf.status` includes the `ADJ_NANO` flag, then `buf.time.tv_usec` is interpreted as a nanosecond value; otherwise it is interpreted as microseconds.

The value of `buf.time` is the sum of its two fields, but the field `buf.time.tv_usec` must always be nonnegative. The following example shows how to normalize a timeval with nanosecond resolution.

```
while (buf.time.tv_usec < 0) {  
    buf.time.tv_sec -= 1;  
    buf.time.tv_usec += 1000000000;
```

}

ADJ_MICRO (since Linux 2.6.26)

Select microsecond resolution.

ADJ_NANO (since Linux 2.6.26)

Select nanosecond resolution. Only one of ADJ_MICRO and ADJ_NANO should be specified.

ADJ_TAI (since Linux 2.6.26)

Set TAI (Atomic International Time) offset from buf.constant.

ADJ_TAI should not be used in conjunction with ADJ_TIMECONST, since the latter mode also employs the buf.constant field.

For a complete explanation of TAI and the difference between TAI and UTC, see BIPM

ADJ_TICK

Set tick value from buf.tick.

Alternatively, modes can be specified as either of the following (multibit mask) values, in which case other bits should not be specified in modes:

ADJ_OFFSET_SINGLESHOT

Old-fashioned adjtime(3): (gradually) adjust time by value specified in buf.offset, which specifies an adjustment in microseconds.

ADJ_OFFSET_SS_READ (functional since Linux 2.6.28)

Return (in buf.offset) the remaining amount of time to be adjusted after an earlier

ADJ_OFFSET_SINGLESHOT operation. This feature was added in Linux 2.6.24, but did not work correctly until Linux 2.6.28.

Ordinary users are restricted to a value of either 0 or ADJ_OFFSET_SS_READ for modes. Only the superuser may set any parameters.

The buf.status field is a bit mask that is used to set and/or retrieve status bits associated

with the NTP implementation. Some bits in the mask are both readable and settable, while others are read-only.

STA_PLL (read-write)

Enable phase-locked loop (PLL) updates via ADJ_OFFSET.

STA_PPSFREQ (read-write)

Enable PPS (pulse-per-second) frequency discipline.

STA_PPSTIME (read-write)

Enable PPS time discipline.

STA_FLL (read-write)

Select frequency-locked loop (FLL) mode.

STA_INS (read-write)

Insert a leap second after the last second of the UTC day, thus extending the last minute of the day by one second. Leap-second insertion will occur each day, so long as this flag remains set.

STA_DEL (read-write)

Delete a leap second at the last second of the UTC day. Leap second deletion will occur each day, so long as this flag remains set.

STA_UNSYNC (read-write)

Clock unsynchronized.

STA_FREQHOLD (read-write)

Hold frequency. Normally adjustments made via ADJ_OFFSET result in dampened frequency adjustments also being made. So a single call corrects the current offset, but as offsets in the same direction are made repeatedly, the small frequency adjustments will accumulate to fix the long-term skew.

This flag prevents the small frequency adjustment from being made when correcting for an ADJ_OFFSET value.

STA_PPSSIGNAL (read-only)

A valid PPS (pulse-per-second) signal is present.

STA_PPSJITTER (read-only)

PPS signal jitter exceeded.

STA_PPSWANDER (read-only)

PPS signal wander exceeded.

STA_PPSERROR (read-only)

PPS signal calibration error.

STA_CLOCKERR (read-only)

Clock hardware fault.

STA_NANO (read-only; since Linux 2.6.26)

Resolution (0 = microsecond, 1 = nanoseconds). Set via ADJ_NANO, cleared via ADJ_MI? CRO.

STA_MODE (since Linux 2.6.26)

Mode (0 = Phase Locked Loop, 1 = Frequency Locked Loop).

STA_CLK (read-only; since Linux 2.6.26)

Clock source (0 = A, 1 = B); currently unused.

Attempts to set read-only status bits are silently ignored.

clock_adjtime ()

The clock_adjtime() system call (added in Linux 2.6.39) behaves like adjtimex() but takes an additional clk_id argument to specify the particular clock on which to act.

ntp_adjtime ()

The ntp_adjtime() library function (described in the NTP "Kernel Application Program API", KAPI) is a more portable interface for performing the same task as adjtimex(). Other than the following points, it is identical to adjtimex():

- ? The constants used in modes are prefixed with "MOD_" rather than "ADJ_", and have the same suffixes (thus, MOD_OFFSET, MOD_FREQUENCY, and so on), other than the exceptions noted in the following points.
- ? MOD_CLKA is the synonym for ADJ_OFFSET_SINGLESHOT.
- ? MOD_CLKB is the synonym for ADJ_TICK.
- ? There is no synonym for ADJ_OFFSET_SS_READ, which is not described in the KAPI.

RETURN VALUE

On success, adjtimex() and ntp_adjtime() return the clock state; that is, one of the following values:

TIME_OK Clock synchronized, no leap second adjustment pending.

TIME_INS Indicates that a leap second will be added at the end of the UTC day.

TIME_DEL Indicates that a leap second will be deleted at the end of the UTC day.

TIME_OOP Insertion of a leap second is in progress.

TIME_WAIT A leap-second insertion or deletion has been completed. This value will be returned until the next ADJ_STATUS operation clears the STA_INS and STA_DEL flags.

TIME_ERROR The system clock is not synchronized to a reliable server. This value is returned when any of the following holds true:

- ? Either STA_UNSYNC or STA_CLOCKERR is set.
- ? STA_PPSSIGNAL is clear and either STA_PPSFREQ or STA_PPSTIME is set.
- ? STA_PPSTIME and STA_PPSJITTER are both set.
- ? STA_PPSFREQ is set and either STA_PPSWANDER or STA_PPSJITTER is set.

The symbolic name TIME_BAD is a synonym for TIME_ERROR, provided for backward compatibility.

On failure, these calls return -1 and set errno to indicate the error.

EFAULT buf does not point to writable memory.

EINVAL (before Linux 2.6.26)

EINVAL (before Linux 2.6.26)

EINVAL An attempt was made to set buf.status to a value other than those listed above.

EOPNOTSUPP

The given clk id does not support adjustment.

EPERM buf.modes is neither 0 nor ADJ_OFFSET_SS_READ, and the caller does not have sufficient privilege. Under Linux, the CAP_SYS_TIME capability is required.

ATTRIBUTES

For an explanation of the terms used in this section, see `attributes(7)`.

[illegible]

?	Interface	?	Attribute	?	Value	?
---	-----------	---	-----------	---	-------	---

[illegible]

? ntp_adjtime() ? Thread safety ? MT-Safe ?

Page 7/8

STANDARDS

adjtimex()

clock_adjtime()

Linux.

The preferred API for the NTP daemon is ntp_adjtime().

NOTES

In struct timex, freq, ppsfreq, and stabil are ppm (parts per million) with a 16-bit fractional part, which means that a value of 1 in one of those fields actually means 2^{-16} ppm, and $2^{16}=65536$ is 1 ppm. This is the case for both input values (in the case of freq) and output values.

The leap-second processing triggered by STA_INS and STA_DEL is done by the kernel in timer context. Thus, it will take one tick into the second for the leap second to be inserted or deleted.

SEE ALSO

clock_gettime(2), clock_settime(2), settimeofday(2), adjtime(3), ntp_gettime(3), capabilities(7), time(7), adjtimex(8), hwclock(8)

NTP "Kernel Application Program Interface"

Linux man-pages 6.17

2026-02-08

adjtimex(2)