



Linux Ubuntu 26.04 Manual Pages on command 'error_print_progname.3'

\$ man error_print_progname.3

error(3) Library Functions Manual error(3)

NAME

error, error_at_line, error_message_count, error_one_per_line, error_print_progname - glibc
error reporting functions

LIBRARY

Standard C library (libc, -lc)

SYNOPSIS

```
#include <error.h>

void error(int status, int errnum, const char *format, ...);

void error_at_line(int status, int errnum, const char *file,
                  unsigned int line, const char *format, ...);

extern unsigned int error_message_count;

extern int error_one_per_line;

extern typeof(void (void)) *error_print_progname;
```

DESCRIPTION

error() is a general error-reporting function. It flushes stdout, and then outputs to stderr the program name, a colon and a space, the message specified by the printf(3)-style format string format, and, if errnum is nonzero, a second colon and a space followed by the string given by strerror(errnum). Any arguments required for format should follow format in the argument list. The output is terminated by a newline character.

The program name printed by error() is the value of the global variable program_invocation_name(3). program_invocation_name initially has the same value as main()'s argv[0].

The value of this variable can be modified to change the output of error().

The `error_at_line()` function is exactly the same as `error()`, except for the addition of the arguments `file` and `line`. The output produced is as for `error()`, except that after the program name are written: a colon, the value of `file`, a colon, and the value of `line`. The preprocessor values `__LINE__` and `__FILE__` may be useful when calling `error_at_line()`, but other values can also be used. For example, these arguments could refer to a location in an input file.

The global variable `error_message_count` counts the number of messages that have been output by `error()` and `error_at_line()`.

ATTRIBUTES

[illegible]

Page 2/3

STANDARDS

GNU.

SEE ALSO

[err\(3\)](#), [errno\(3\)](#), [exit\(3\)](#), [perror\(3\)](#), [program_invocation_name\(3\)](#), [strerror\(3\)](#)

Linux man-pages 6.17

2026-02-08

[error\(3\)](#)