



## ***Linux Ubuntu 26.04 Manual Pages on command 'getutid\_r.3'***

### ***\$ man getutid\_r.3***

getutent(3)                      Library Functions Manual                      getutent(3)

#### NAME

getutent, getutid, getutline, pututline, setutent, endutent, utmpname - access utmp file en?

tries

#### LIBRARY

Standard C library (libc, -lc)

#### SYNOPSIS

```
#include <utmp.h>

struct utmp *getutent(void);

struct utmp *getutid(const struct utmp *ut);

struct utmp *getutline(const struct utmp *ut);

struct utmp *pututline(const struct utmp *ut);

void setutent(void);

void endutent(void);

int utmpname(const char *path);
```

#### DESCRIPTION

New applications should use the POSIX.1-specified "utmpx" versions of these functions; see STANDARDS.

utmpname() sets the pathname of the utmp-format file for the other utmp functions to access.

If utmpname() is not used to set the pathname before the other functions are used, they as?

sume \_PATH\_UTMP, as defined in <paths.h>.

setutent() rewinds the file pointer to the beginning of the utmp file. It is generally a

good idea to call it before any of the other functions.

endutent() closes the utmp file. It should be called when the user code is done accessing the file with the other functions.

getutent() reads a line from the current file position in the utmp file. It returns a pointer to a structure containing the fields of the line. The definition of this structure is shown in utmp(5).

getutid() searches forward from the current file position in the utmp file based upon ut.

If ut->ut\_type is one of RUN\_LVL, BOOT\_TIME, NEW\_TIME, or OLD\_TIME, getutid() will find the first entry whose ut\_type field matches ut->ut\_type. If ut->ut\_type is one of INIT\_PROCESS, LOGIN\_PROCESS, USER\_PROCESS, or DEAD\_PROCESS, getutid() will find the first entry whose ut\_id field matches ut->ut\_id.

getutline() searches forward from the current file position in the utmp file. It scans entries whose ut\_type is USER\_PROCESS or LOGIN\_PROCESS and returns the first one whose ut\_line field matches ut->ut\_line.

pututline() writes the utmp structure ut into the utmp file. It uses getutid() to search for the proper place in the file to insert the new entry. If it cannot find an appropriate slot for ut, pututline() will append the new entry to the end of the file.

## RETURN VALUE

getutent(), getutid(), and getutline() return a pointer to a struct utmp on success, and NULL on failure (which includes the "record not found" case). This struct utmp is allocated in static storage, and may be overwritten by subsequent calls.

On success pututline() returns ut; on failure, it returns NULL.

utmpname() returns 0 if the new name was successfully stored, or -1 on failure.

On failure, these functions errno set to indicate the error.

## ERRORS

ENOMEM Out of memory.

ESRCH Record not found.

setutent(), pututline(), and the getut\*() functions can also fail for the reasons described in open(2).

## FILES

/var/run/utmp

database of currently logged-in users

/var/log/wtmp

database of past user logins

## ATTRIBUTES

For an explanation of the terms used in this section, see `attributes(7)`.

[illegible]

| ? | Interface | ? | Attribute | ? | Value | ? |
|---|-----------|---|-----------|---|-------|---|
|   |           |   |           |   |       |   |

[illegible]

|              |                             |                               |   |
|--------------|-----------------------------|-------------------------------|---|
| ? getutent() | ? Thread safety ? MT-Unsafe | init race:utent race:utentbuf | ? |
|--------------|-----------------------------|-------------------------------|---|

? ? ? sig:ALRM timer ?

[illegible]

? getutid(), getutline() ? Thread safety ? MT-Unsafe init race:utent sig:ALRM timer ?

[illegible]

? pututline() ? Thread safety ? MT-Unsafe race:utent sig:ALRM timer ?

[illegible]

|   |                           |                 |                      |   |
|---|---------------------------|-----------------|----------------------|---|
| ? | setutent(), endutent(), ? | Thread safety ? | MT-Unsafe race:utent | ? |
|---|---------------------------|-----------------|----------------------|---|

|              |   |   |   |
|--------------|---|---|---|
| ? utmpname() | ? | ? | ? |
|--------------|---|---|---|

[illegible]

In the above table, utent in race:uent signifies that if any of the functions setuent(),

getutent(), getutid(), getutline(), pututline(), utmpname(), or endutent() are used in par?

allel in different threads of a program, then data races could occur.

## STANDARDS

None.

## HISTORY

XPG2, SVr4.

In XPG2 and SVID 2 the function `pututline()` is documented to return void, and that is what

it does on many systems (AIX, HP-UX). HP-UX introduces a new function `_pututline()` with the prototype given above for `pututline()`.

All these functions are obsolete now on non-Linux systems. POSIX.1-2001 and POSIX.1-2008, following SUSv1, does not have any of these functions, but instead uses

```
#include <utmpx.h>
```

```
struct utmpx *getutxent(void);
```

```
struct utmpx *getutxid(const struct utmpx *);
```

```
struct utmpx *getutxline(const struct utmpx *);
```

```
struct utmpx *pututxline(const struct utmpx *);
```

```
void setutxent(void);
```

```
void endutxent(void);
```

These functions are provided by glibc, and perform the same task as their equivalents with? out the "x", but use struct utmpx, defined on Linux to be the same as struct utmp. For com? pleteness, glibc also provides utmpxname(), although this function is not specified by POSIX.1.

On some other systems, the utmpx structure is a superset of the utmp structure, with addi? tional fields, and larger versions of the existing fields, and parallel files are main? tained, often /var/\*/utmpx and /var/\*/wtmpx.

Linux glibc on the other hand does not use a parallel utmpx file since its utmp structure is already large enough. The "x" functions listed above are just aliases for their counter? parts without the "x" (e.g., getutxent() is an alias for getutent()).

## NOTES

### glibc notes

The above functions are not thread-safe. glibc adds reentrant versions

```
#include <utmp.h>
```

```
int getutent_r(struct utmp *ubuf, struct utmp **ubufp);
```

```
int getutid_r(struct utmp *ut,  
              struct utmp *ubuf, struct utmp **ubufp);
```

```
int getutline_r(struct utmp *ut,  
                struct utmp *ubuf, struct utmp **ubufp);
```

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

getutent\_r(), getutid\_r(), getutline\_r():

```
_GNU_SOURCE
```

```
|| /* Since glibc 2.19: */ _DEFAULT_SOURCE
```

```
|| /* glibc <= 2.19: */ _SVID_SOURCE || _BSD_SOURCE
```

These functions are GNU extensions, analogs of the functions of the same name without the \_r suffix. The ubuf argument gives these functions a place to store their result. On success, they return 0, and a pointer to the result is written in \*ubufp. On error, these functions return -1. There are no utmpx equivalents of the above functions. (POSIX.1 does not specify such functions.)

## EXAMPLES

The following example adds and removes a utmp record, assuming it is run from within a pseudo terminal. For usage in a real application, you should check the return values of

getpwuid(3) and ttyname(3).

```
#include <err.h>

#include <pwd.h>

#include <stdlib.h>

#include <string.h>

#include <time.h>

#include <unistd.h>

#include <utmp.h>

int

main(void)

{
    struct utmp entry;

    if (system("echo before adding entry:;who") == -1)
        err(EXIT_FAILURE, "system");

    entry.ut_type = USER_PROCESS;

    entry.ut_pid = getpid();

    strcpy(entry.ut_line, ttyname(STDIN_FILENO) + strlen("/dev/"));

    /* only correct for ptys named /dev/tty[pqr][0-9a-z] */

    strcpy(entry.ut_id, ttyname(STDIN_FILENO) + strlen("/dev/tty"));

    entry.ut_time = time(NULL);

    strcpy(entry.ut_user, getpwuid(getuid())->pw_name);

    memset(entry.ut_host, 0, UT_HOSTSIZE);

    entry.ut_addr = 0;

    setutent();

    if (pututline(&entry) == NULL)
        err(EXIT_FAILURE, "pututline");

    if (system("echo after adding entry:;who") == -1)
        err(EXIT_FAILURE, "system");

    entry.ut_type = DEAD_PROCESS;

    memset(entry.ut_line, 0, UT_LINESIZE);

    entry.ut_time = 0;

    memset(entry.ut_user, 0, UT_NAMESIZE);

    setutent();
```

```
if (pututline(&entry) == NULL)
    err(EXIT_FAILURE, "pututline");
if (system("echo after removing entry:;who") == -1)
    err(EXIT_FAILURE, "system");
endutent();
exit(EXIT_SUCCESS);
}
```

#### SEE ALSO

getutmp(3), utmp(5)

Linux man-pages 6.17

2026-02-08

getutent(3)