

NAME

`docker-container-run` - Run a command in a new container

SYNOPSIS

`docker container run [OPTIONS] IMAGE [COMMAND] [ARG...]`

DESCRIPTION

Alias for `docker run`.

OPTIONS

`--add-host=` Add a custom host-to-IP mapping (host:ip)

`-a, --attach=` Attach to STDIN, STDOUT or STDERR

`--blkio-weight=0` Block IO (relative weight), between 10 and 1000, or 0 to disable (default 0)

`--blkio-weight-device=[]` Block IO weight (relative device weight)

`--cap-add=` Add Linux capabilities

`--cap-drop=` Drop Linux capabilities

`--cgroup-parent=""` Optional parent cgroup for the container

`--cgroupns=""` Cgroup namespace to use (host|private)
default-cgroupns-mode option on the daemon (default)

`--cidfile=""` Write the container ID to the file

`--cpu-count=0` CPU count (Windows only)

`--cpu-percent=0` CPU percent (Windows only)

`--cpu-period=0` Limit CPU CFS (Completely Fair Scheduler) period

`--cpu-quota=0` Limit CPU CFS (Completely Fair Scheduler) quota

`--cpu-rt-period=0` Limit CPU real-time period in microseconds

`--cpu-rt-runtime=0` Limit CPU real-time runtime in microseconds

`-c, --cpu-shares=0` CPU shares (relative weight)

`--cpus=` Number of CPUs

--cpuset-cpus=""	CPUs in which to allow execution (0-3, 0,1)
--cpuset-mems=""	MEMs in which to allow execution (0-3, 0,1)
-d, --detach[=false]	Run container in background and print container ID
--detach-keys=""	Override the key sequence for detaching a container
--device=	Add a host device to the container
--device-cgroup-rule=	Add a rule to the cgroup allowed devices list
--device-read-bps=[]	Limit read rate (bytes per second) from a device
--device-read-iops=[]	Limit read rate (IO per second) from a device
--device-write-bps=[]	Limit write rate (bytes per second) to a device
--device-write-iops=[]	Limit write rate (IO per second) to a device
--disable-content-trust[=true]	Skip image verification
--dns=	Set custom DNS servers
--dns-option=	Set DNS options
--dns-search=	Set custom DNS search domains
--domainname=""	Container NIS domain name
--entrypoint=""	Overwrite the default ENTRYPOINT of the image
-e, --env=	Set environment variables
--env-file=	Read in a file of environment variables
--expose=	Expose a port or a range of ports
--gpus=	GPU devices to add to the container ('all' to pass all GPUs)
--group-add=	Add additional groups to join
--health-cmd=""	Command to run to check health
--health-interval=0s	Time between running the check (ms s m h) (default 0s)

--health-retries=0 Consecutive failures needed to report unhealthy

--health-start-period=0s Start period for the container to initialize before starting health-retries
countdown (ms|s|m|h) (default 0s)

--health-timeout=0s Maximum time to allow one check to run (ms|s|m|h) (default 0s)

--help[=false] Print usage

-h, --hostname="" Container host name

--init[=false] Run an init inside the container that forwards signals and reaps processes

-i, --interactive[=false] Keep STDIN open even if not attached

--io-maxbandwidth=0 Maximum IO bandwidth limit for the system drive (Windows only)

--io-maxiops=0 Maximum IOps limit for the system drive (Windows only)

--ip="" IPv4 address (e.g., 172.30.100.104)

--ip6="" IPv6 address (e.g., 2001:db8::33)

--ipc="" IPC mode to use

--isolation="" Container isolation technology

--kernel-memory=0 Kernel memory limit

-l, --label= Set meta data on a container

--label-file= Read in a line delimited file of labels

--link= Add link to another container

--link-local-ip= Container IPv4/IPv6 link-local addresses

--log-driver="" Logging driver for the container

--log-opt= Log driver options

--mac-address="" Container MAC address (e.g., 92:d0:c6:0a:29:33)

-m, --memory=0 Memory limit

--memory-reservation=0 Memory soft limit

--memory-swap=0	Swap limit equal to memory plus swap: '-1' to enable unlimited swap
--memory-swappiness=-1	Tune container memory swappiness (0 to 100)
--mount=	Attach a filesystem mount to the container
--name=""	Assign a name to the container
--network=	Connect a container to a network
--network-alias=	Add network-scoped alias for the container
--no-healthcheck[=false]	Disable any container-specified HEALTHCHECK
--oom-kill-disable[=false]	Disable OOM Killer
--oom-score-adj=0	Tune host's OOM preferences (-1000 to 1000)
--pid=""	PID namespace to use
--pids-limit=0	Tune container pids limit (set -1 for unlimited)
--platform=""	Set platform if server is multi-platform capable
--privileged[=false]	Give extended privileges to this container
-p, --publish=	Publish a container's port(s) to the host
-P, --publish-all[=false]	Publish all exposed ports to random ports
--pull="missing"	Pull image before running ("always" "missing" "never")
--read-only[=false]	Mount the container's root filesystem as read only
--restart="no"	Restart policy to apply when a container exits
--rm[=false]	Automatically remove the container when it exits
--runtime=""	Runtime to use for this container
--security-opt=	Security Options
--shm-size=0	Size of /dev/shm
--sig-proxy[=true]	Proxy received signals to the process

--stop-signal="SIGTERM" Signal to stop a container

--stop-timeout=0 Timeout (in seconds) to stop a container

--storage-opt= Storage driver options for the container

--sysctl=map[] Sysctl options

--tmpfs= Mount a tmpfs directory

-t, --tty[=false] Allocate a pseudo-TTY

--ulimit=[] Ulimit options

-u, --user="" Username or UID (format: [::])

--userns="" User namespace to use

--uts="" UTS namespace to use

-v, --volume= Bind mount a volume

--volume-driver="" Optional volume driver for the container

--volumes-from= Mount volumes from the specified container(s)

-w, --workdir="" Working directory inside the container

SEE ALSO**docker-container(1)**