

NAME

systemd-udev.service, systemd-udev-control.socket, systemd-udev-kernel.socket, systemd-udev – Device event managing daemon

SYNOPSIS

systemd-udev.service

systemd-udev-control.socket

systemd-udev-kernel.socket

/lib/systemd/systemd-udev [**--daemon**] [**--debug**] [**--children-max=**] [**--exec-delay=**] [**--event-timeout=**] [**--resolve-names=early|late|never**] [**--version**] [**--help**]

DESCRIPTION

systemd-udev listens to kernel uevents. For every event, **systemd-udev** executes matching instructions specified in udev rules. See **udev(7)**.

The behavior of the daemon can be configured using **udev.conf(5)**, its command line options, environment variables, and on the kernel command line, or changed dynamically with **udevadm control**.

OPTIONS

-d, --daemon

Detach and run in the background.

-D, --debug

Print debug messages to standard error.

-c, --children-max=

Limit the number of events executed in parallel.

-e, --exec-delay=

Delay the execution of *RUN* instructions by the given number of seconds. This option might be useful when debugging system crashes during coldplug caused by loading non-working kernel modules.

-t, --event-timeout=

Set the number of seconds to wait for events to finish. After this time, the event will be terminated. The default is 180 seconds.

-N, --resolve-names=

Specify when **systemd-udev** should resolve names of users and groups. When set to **early** (the default), names will be resolved when the rules are parsed. When set to **late**, names will be resolved for every event. When set to **never**, names will never be resolved and all devices will be owned by root.

-h, --help

Print a short help text and exit.

--version

Print a short version string and exit.

KERNEL COMMAND LINE

Parameters starting with "rd." will be read when **systemd-udev** is used in an initrd.

udev.log_priority=, *rd.udev.log_priority=*

Set the log level.

udev.children_max=, *rd.udev.children_max=*

Limit the number of events executed in parallel.

udev.exec_delay=, *rd.udev.exec_delay=*

Delay the execution of *RUN* instructions by the given number of seconds. This option might be useful when debugging system crashes during coldplug caused by loading non-working kernel modules.

udev.event_timeout=, *rd.udev.event_timeout=*

Wait for events to finish up to the given number of seconds. This option might be useful if events are terminated due to kernel drivers taking too long to initialize.

net.ifnames=

Network interfaces are renamed to give them predictable names when possible. It is enabled by default; specifying 0 disables it.

net.naming-scheme=

Network interfaces are renamed to give them predictable names when possible (unless *net.ifnames=0* is specified, see above). With this kernel command line option it is possible to pick a specific version of this algorithm and override the default chosen at compilation time. Expects one of the naming scheme identifiers listed in **systemd.net-naming-scheme(7)**, or "latest" to select the latest scheme known (to this particular version of systemd-udev.service).

Note that selecting a specific scheme is not sufficient to fully stabilize interface naming: the naming is generally derived from driver attributes exposed by the kernel. As the kernel is updated, previously missing attributes systemd-udev.service is checking might appear, which affects older name derivation algorithms, too.

SEE ALSO

udev.conf(5), **udev(7)**, **udevadm(8)**