

CRONTAB(1)

General Commands Manual

CRONTAB(1)

NAME

crontab - maintain crontab files for individual users (Vixie Cron)

SYNOPSIS

crontab [-h]

crontab [-u user] [-n] file

crontab [-u user] [-i] { -e | -l | -r }

DESCRIPTION

crontab is the program used to install, deinstall or list the tables used to drive the cron(8) daemon in Vixie Cron. Each user can have their own crontab, and though these are files in `/var/spool/cron/crontabs`, they are not intended to be edited directly.

If the `/etc/cron.allow` file exists, then you must be listed (one user per line) therein in order to be allowed to use this command. If the `/etc/cron.allow` file does not exist but the `/etc/cron.deny` file does exist, then you must not be listed in the `/etc/cron.deny` file in order to use this command.

If neither of these files exists, then depending on site-dependent configuration parameters, only the super user will be allowed to use this

Linux UBUNTU Manual Pages

If both files exist then `/etc/cron.allow` takes precedence. Which means that `/etc/cron.deny` is not considered and your user must be listed in `/etc/cron.allow` in order to be able to use the crontab.

Regardless of the existence of any of these files, the root administrative user is always allowed to setup a crontab. For standard Debian systems, all users may use this command.

If the `-h` option is given, `crontab` shows a help message and quits immediately.

If the `-u` option is given, it specifies the name of the user whose crontab is to be used (when listing) or modified (when editing). If this option is not given, `crontab` examines "your" crontab, i.e., the crontab of the person executing the command. Note that `su(8)` can confuse `crontab` and that if you are running inside of `su(8)` you should always use the `-u` option for safety's sake.

The first form of this command is used to install a new crontab from some named file or standard input if the pseudo-filename ```-` is given.

If the `-n` option is given, it means "dry run": `crontab` examines "your"

correct, but nothing is written to any crontab.

The `-l` option causes the current crontab to be displayed on standard output. See the note under DEBIAN SPECIFIC below.

The `-r` option causes the current crontab to be removed.

The `-e` option is used to edit the current crontab using the editor specified by the `VISUAL` or `EDITOR` environment variables. After you exit from the editor, the modified crontab will be installed automatically. If neither of the environment variables is defined, then the default editor `/usr/bin/editor` is used.

The `-i` option modifies the `-r` option to prompt the user for a 'y/Y' response before actually removing the crontab.

DEBIAN SPECIFIC

The "out-of-the-box" behaviour for `crontab -l` is to display the three line "DO NOT EDIT THIS FILE" header that is placed at the beginning of the crontab when it is installed. The problem is that it makes the sequence

`crontab -l | crontab -`

pain to scripts that use sed to edit a crontab. Therefore, the default behaviour of the -l option has been changed to not output such header. You may obtain the original behaviour by setting the environment variable CRONTAB_NOHEADER to 'N', which will cause the crontab -l command to emit the extraneous header.

HIGHLIGHTING THE OUTPUT of crontab -l

The command crontab -l outputs plain text. When a tty can support ANSI sequences to colourise this text, one can highlight the output, by calling: crontab -l | spc -t crontab when the tty background is dark, or crontab -l | spc -t crontab-light when this background is light.

The highlighting scheme can be modified by using customised versions of files `/etc/supercat/spcrc-crontab*`

SEE ALSO

crontab(5), cron(8), spc(1)

FILES

`/etc/cron.allow`

`/etc/cron.deny`

`/var/spool/cron/crontabs`

The files `/etc/cron.allow` and `/etc/cron.deny` if they exist, must be ei?

then cron will deny access to all users until the permissions are fixed.

There is one file for each user's crontab under the `/var/spool/cron/crontabs` directory. Users are not allowed to edit the files under that directory directly to ensure that only users allowed by the system to run periodic tasks can add them, and only syntactically correct crontabs will be written there. This is enforced by having the directory writable only by the crontab group and configuring crontab command with the setgid bit set for that specific group.

STANDARDS

The crontab command conforms to IEEE Std1003.2-1992 ("POSIX"). This new command syntax differs from previous versions of Vixie Cron, as well as from the classic SVR3 syntax.

DIAGNOSTICS

A fairly informative usage message appears if you run it with a bad command line.

cron requires that each entry in a crontab end in a newline character.

If the last entry in a crontab is missing the newline, cron will consider the crontab (at least partially) broken and refuse to install it.

account name. Crontab jobs will not be run for users whose accounts have been renamed either due to changes in the local system or because they are managed through a central user database (external to the system, for example an LDAP directory).

AUTHOR

Paul Vixie <[a href="mailto:paul@vix.com">paul@vix.com> is the author of cron and original creator of this manual page. This page has also been modified for Debian by Steve Greenland, Javier Fernandez-Sanguino and Christian Kastner.