



Rocky Enterprise Linux 9.2 Manual Pages on command 'xdr_authunix_parms.3'

C:\>man xdr_authunix_parms.3

RPC(3) Linux Programmer's Manual RPC(3)

NAME

rpc - library routines for remote procedure calls

SYNOPSIS AND DESCRIPTION

These routines allow C programs to make procedure calls on other machines across the network. First, the client calls a procedure to send a data packet to the server. Upon receipt of the packet, the server calls a dispatch routine to perform the requested service, and then sends back a reply. Finally, the procedure call returns to the client.

To take use of these routines, include the header file <rpc/rpc.h>.

The prototypes below make use of the following types:

```
typedef int bool_t;
typedef bool_t (*xdrproc_t) (XDR *, void *, ...);
typedef bool_t (*resultproc_t) (caddr_t resp,
                                struct sockaddr_in *raddr);
```

See the header files for the declarations of the AUTH, CLIENT, SVCXPRT, and XDR types.

```
void auth_destroy(AUTH *auth);
```

A macro that destroys the authentication information associated with auth.

Destruction usually involves deallocation of private data structures. The

use of auth is undefined after calling auth_destroy().

```
AUTH *authnone_create(void);
```

Create and return an RPC authentication handle that passes nonusable authentication information with each remote procedure call. This is the default authentication used by RPC.

```
AUTH *authunix_create(char *host, int uid, int gid,  
    int len, int *aup_gids);
```

Create and return an RPC authentication handle that contains authentication information. The parameter `host` is the name of the machine on which the information was created; `uid` is the user's user ID; `gid` is the user's current group ID; `len` and `aup_gids` refer to a counted array of groups to which the user belongs. It is easy to impersonate a user.

```
AUTH *authunix_create_default(void);
```

Calls `authunix_create()` with the appropriate parameters.

```
int callrpc(char *host, unsigned long prognum,  
    unsigned long versnum, unsigned long procnum,  
    xdrproc_t inproc, char *in,  
    xdrproc_t outproc, char *out);
```

Call the remote procedure associated with `prognum`, `versnum`, and `procnum` on the machine, `host`. The parameter `in` is the address of the procedure's argument(s), and `out` is the address of where to place the result(s); `inproc` is used to encode the procedure's parameters, and `outproc` is used to decode the procedure's results. This routine returns zero if it succeeds, or the value of `enum clnt_stat` cast to an integer if it fails. The routine `clnt_perrno()` is handy for translating failure statuses into messages.

Warning: calling remote procedures with this routine uses UDP/IP as a transport; see `clntudp_create()` for restrictions. You do not have control of timeouts or authentication using this routine.

```
enum clnt_stat clnt_broadcast(unsigned long prognum,  
    unsigned long versnum, unsigned long procnum,  
    xdrproc_t inproc, char *in,  
    xdrproc_t outproc, char *out,  
    resultproc_t eachresult);
```

Like `callrpc()`, except the call message is broadcast to all locally connected broadcast nets. Each time it receives a response, this routine calls

eachresult(), whose form is:

```
eachresult(char *out, struct sockaddr_in *addr);
```

where out is the same as out passed to clnt_broadcast(), except that the remote procedure's output is decoded there; addr points to the address of the machine that sent the results. If eachresult() returns zero, clnt_broadcast() waits for more replies; otherwise it returns with appropriate status.

Warning: broadcast sockets are limited in size to the maximum transfer unit of the data link. For ethernet, this value is 1500 bytes.

```
enum clnt_stat clnt_call(CLIENT *clnt, unsigned long procnum,  
                        xdrproc_t inproc, char *in,  
                        xdrproc_t outproc, char *out,  
                        struct timeval tout);
```

A macro that calls the remote procedure procnum associated with the client handle, clnt, which is obtained with an RPC client creation routine such as clnt_create(). The parameter in is the address of the procedure's argument(s), and out is the address of where to place the result(s); inproc is used to encode the procedure's parameters, and outproc is used to decode the procedure's results; tout is the time allowed for results to come back.

```
clnt_destroy(CLIENT *clnt);
```

A macro that destroys the client's RPC handle. Destruction usually involves deallocation of private data structures, including clnt itself. Use of clnt is undefined after calling clnt_destroy(). If the RPC library opened the associated socket, it will close it also. Otherwise, the socket remains open.

```
CLIENT *clnt_create(char *host, unsigned long prog,  
                   unsigned long vers, char *proto);
```

Generic client creation routine. host identifies the name of the remote host where the server is located. proto indicates which kind of transport protocol to use. The currently supported values for this field are ?udp? and ?tcp?. Default timeouts are set, but can be modified using clnt_control().

Warning: using UDP has its shortcomings. Since UDP-based RPC messages can hold only up to 8 Kbytes of encoded data, this transport cannot be used for

procedures that take large arguments or return huge results.

```
bool_t clnt_control(CLIENT *cl, int req, char *info);
```

A macro used to change or retrieve various information about a client object. req indicates the type of operation, and info is a pointer to the information. For both UDP and TCP, the supported values of req and their argument types and what they do are:

```
CLSET_TIMEOUT struct timeval // set total timeout
```

```
CLGET_TIMEOUT struct timeval // get total timeout
```

Note: if you set the timeout using clnt_control(), the timeout parameter passed to clnt_call() will be ignored in all future calls.

```
CLGET_SERVER_ADDR struct sockaddr_in // get server's address
```

The following operations are valid for UDP only:

```
CLSET_RETRY_TIMEOUT struct timeval // set the retry timeout
```

```
CLGET_RETRY_TIMEOUT struct timeval // get the retry timeout
```

The retry timeout is the time that "UDP RPC" waits for the server to reply before retransmitting the request.

```
clnt_freeres(CLIENT *clnt, xdrproc_t outproc, char *out);
```

A macro that frees any data allocated by the RPC/XDR system when it decoded the results of an RPC call. The parameter out is the address of the results, and outproc is the XDR routine describing the results. This routine returns one if the results were successfully freed, and zero otherwise.

```
void clnt_geterr(CLIENT *clnt, struct rpc_err *errp);
```

A macro that copies the error structure out of the client handle to the structure at address errp.

```
void clnt_pcreateerror(char *s);
```

Print a message to standard error indicating why a client RPC handle could not be created. The message is prepended with string s and a colon. Used when a clnt_create(), clntudp_create(), clnttcp_create(), or clntudp_create() call fails.

```
void clnt_perrno(enum clnt_stat stat);
```

Print a message to standard error corresponding to the condition indicated by stat. Used after callrpc().

```
clnt_perror(CLIENT *clnt, char *s);
```

Print a message to standard error indicating why an RPC call failed; `clnt` is the handle used to do the call. The message is prepended with string `s` and a colon. Used after `clnt_call()`.

```
char *clnt_spcreateerror(char *s);
```

Like `clnt_pcreateerror()`, except that it returns a string instead of printing to the standard error.

Bugs: returns pointer to static data that is overwritten on each call.

```
char *clnt_sperrno(enum clnt_stat stat);
```

Take the same arguments as `clnt_perrno()`, but instead of sending a message to the standard error indicating why an RPC call failed, return a pointer to a string which contains the message. The string ends with a NEWLINE.

`clnt_sperrno()` is used instead of `clnt_perrno()` if the program does not have a standard error (as a program running as a server quite likely does not), or if the programmer does not want the message to be output with `printf(3)`, or if a message format different than that supported by `clnt_perrno()` is to be used. Note: unlike `clnt_sperror()` and `clnt_spcreateerror()`, `clnt_sperrno()` returns pointer to static data, but the result will not get overwritten on each call.

```
char *clnt_sperror(CLIENT *rpch, char *s);
```

Like `clnt_perror()`, except that (like `clnt_sperrno()`) it returns a string instead of printing to standard error.

Bugs: returns pointer to static data that is overwritten on each call.

```
CLIENT *clntraw_create(unsigned long prognum, unsigned long versnum);
```

This routine creates a toy RPC client for the remote program `prognum`, version `versnum`. The transport used to pass messages to the service is actually a buffer within the process's address space, so the corresponding RPC server should live in the same address space; see `svcrw_create()`. This allows simulation of RPC and acquisition of RPC overheads, such as round trip times, without any kernel interference. This routine returns NULL if it fails.

```
CLIENT *clnttcp_create(struct sockaddr_in *addr,  
    unsigned long prognum, unsigned long versnum,  
    int *sockp, unsigned int sendsz, unsigned int recvsz);
```

This routine creates an RPC client for the remote program `prognum`, version `versnum`; the client uses TCP/IP as a transport. The remote program is located at Internet address `*addr`. If `addr->sin_port` is zero, then it is set to the actual port that the remote program is listening on (the remote portmap service is consulted for this information). The parameter `sockp` is a socket; if it is `RPC_ANYSOCK`, then this routine opens a new one and sets `sockp`. Since TCP-based RPC uses buffered I/O, the user may specify the size of the send and receive buffers with the parameters `sendsz` and `recvsz`; values of zero choose suitable defaults. This routine returns `NULL` if it fails.

```
CLIENT *clntudp_create(struct sockaddr_in *addr,  
    unsigned long prognum, unsigned long versnum,  
    struct timeval wait, int *sockp);
```

This routine creates an RPC client for the remote program `prognum`, version `versnum`; the client uses UDP/IP as a transport. The remote program is located at Internet address `addr`. If `addr->sin_port` is zero, then it is set to actual port that the remote program is listening on (the remote portmap service is consulted for this information). The parameter `sockp` is a socket; if it is `RPC_ANYSOCK`, then this routine opens a new one and sets `sockp`. The UDP transport resends the call message in intervals of `wait` time until a response is received or until the call times out. The total time for the call to time out is specified by `clnt_call()`.

Warning: since UDP-based RPC messages can hold only up to 8 Kbytes of encoded data, this transport cannot be used for procedures that take large arguments or return huge results.

```
CLIENT *clntudp_bufcreate(struct sockaddr_in *addr,  
    unsigned long prognum, unsigned long versnum,  
    struct timeval wait, int *sockp,  
    unsigned int sendsize, unsigned int recosize);
```

This routine creates an RPC client for the remote program `prognum`, on version `versnum`; the client uses UDP/IP as a transport. The remote program is located at Internet address `addr`. If `addr->sin_port` is zero, then it is set to actual port that the remote program is listening on (the remote portmap

service is consulted for this information). The parameter sockp is a socket; if it is RPC_ANYSOCK, then this routine opens a new one and sets sockp. The UDP transport resends the call message in intervals of wait time until a response is received or until the call times out. The total time for the call to time out is specified by clnt_call().

This allows the user to specify the maximum packet size for sending and receiving UDP-based RPC messages.

```
void get_myaddress(struct sockaddr_in *addr);
```

Stuff the machine's IP address into *addr, without consulting the library routines that deal with /etc/hosts. The port number is always set to htons(PMAPPORT).

```
struct pmaplist *pmap_getmaps(struct sockaddr_in *addr);
```

A user interface to the portmap service, which returns a list of the current RPC program-to-port mappings on the host located at IP address *addr. This routine can return NULL. The command rpcinfo -p uses this routine.

```
unsigned short pmap_getport(struct sockaddr_in *addr,  
                           unsigned long prognum, unsigned long versnum,  
                           unsigned int protocol);
```

A user interface to the portmap service, which returns the port number on which waits a service that supports program number prognum, version versnum, and speaks the transport protocol associated with protocol. The value of protocol is most likely IPPROTO_UDP or IPPROTO_TCP. A return value of zero means that the mapping does not exist or that the RPC system failed to contact the remote portmap service. In the latter case, the global variable rpc_createerr contains the RPC status.

```
enum clnt_stat pmap_rmtcall(struct sockaddr_in *addr,  
                          unsigned long prognum, unsigned long versnum,  
                          unsigned long procnum,  
                          xdrproc_t inproc, char *in,  
                          xdrproc_t outproc, char *out,  
                          struct timeval tout, unsigned long *portp);
```

A user interface to the portmap service, which instructs portmap on the host at IP address *addr to make an RPC call on your behalf to a procedure on

that host. The parameter `*portp` will be modified to the program's port number if the procedure succeeds. The definitions of other parameters are discussed in `callrpc()` and `clnt_call()`. This procedure should be used for a ping and nothing else. See also `clnt_broadcast()`.

```
bool_t pmap_set(unsigned long prognum, unsigned long versnum,  
               unsigned int protocol, unsigned short port);
```

A user interface to the portmap service, which establishes a mapping between the triple `[prognum,versnum,protocol]` and port on the machine's portmap service. The value of `protocol` is most likely `IPPROTO_UDP` or `IPPROTO_TCP`. This routine returns one if it succeeds, zero otherwise. Automatically done by `svc_register()`.

```
bool_t pmap_unset(unsigned long prognum, unsigned long versnum);
```

A user interface to the portmap service, which destroys all mapping between the triple `[prognum,versnum,*]` and ports on the machine's portmap service. This routine returns one if it succeeds, zero otherwise.

```
int registerrpc(unsigned long prognum, unsigned long versnum,  
               unsigned long procnum, char *(*procname)(char *),  
               xdrproc_t inproc, xdrproc_t outproc);
```

Register procedure `procname` with the RPC service package. If a request arrives for program `prognum`, version `versnum`, and procedure `procnum`, `procname` is called with a pointer to its parameter(s); `procname` should return a pointer to its static result(s); `inproc` is used to decode the parameters while `outproc` is used to encode the results. This routine returns zero if the registration succeeded, -1 otherwise.

Warning: remote procedures registered in this form are accessed using the UDP/IP transport; see `svcudp_create()` for restrictions.

```
struct rpc_createerr rpc_createerr;
```

A global variable whose value is set by any RPC client creation routine that does not succeed. Use the routine `clnt_pcreateerror()` to print the reason why.

```
void svc_destroy(SVCXPRT *xpirt);
```

A macro that destroys the RPC service transport handle, `xpirt`. Destruction usually involves deallocation of private data structures, including `xpirt` if?

self. Use of `xprt` is undefined after calling this routine.

`fd_set svc_fdset;`

A global variable reflecting the RPC service side's read file descriptor bit mask; it is suitable as a parameter to the `select(2)` system call. This is of interest only if a service implementor does their own asynchronous event processing, instead of calling `svc_run()`. This variable is read-only (do not pass its address to `select(2)!`), yet it may change after calls to `svc_getreqset()` or any creation routines.

`int svc_fds;`

Similar to `svc_fdset`, but limited to 32 file descriptors. This interface is obsoleted by `svc_fdset`.

`svc_freeargs(SVCXPRT *xprt, xdrproc_t inproc, char *in);`

A macro that frees any data allocated by the RPC/XDR system when it decoded the arguments to a service procedure using `svc_getargs()`. This routine returns 1 if the results were successfully freed, and zero otherwise.

`svc_getargs(SVCXPRT *xprt, xdrproc_t inproc, char *in);`

A macro that decodes the arguments of an RPC request associated with the RPC service transport handle, `xprt`. The parameter `in` is the address where the arguments will be placed; `inproc` is the XDR routine used to decode the arguments. This routine returns one if decoding succeeds, and zero otherwise.

`struct sockaddr_in *svc_getcaller(SVCXPRT *xprt);`

The approved way of getting the network address of the caller of a procedure associated with the RPC service transport handle, `xprt`.

`void svc_getreqset(fd_set *rdfs);`

This routine is of interest only if a service implementor does not call `svc_run()`, but instead implements custom asynchronous event processing. It is called when the `select(2)` system call has determined that an RPC request has arrived on some RPC socket(s); `rdfs` is the resultant read file descriptor bit mask. The routine returns when all sockets associated with the value of `rdfs` have been serviced.

`void svc_getreq(int rdfs);`

Similar to `svc_getreqset()`, but limited to 32 file descriptors. This interface is obsoleted by `svc_getreqset()`.

```
bool_t svc_register(SVCXPRT *xpvt, unsigned long prognum,
    unsigned long versnum,
    void (*dispatch)(svc_req *, SVCXPRT *),
    unsigned long protocol);
```

Associates prognum and versnum with the service dispatch procedure, dispatch. If protocol is zero, the service is not registered with the portmap service. If protocol is nonzero, then a mapping of the triple [prognum,versnum,protocol] to xpvt->xp_port is established with the local portmap service (generally protocol is zero, IPPROTO_UDP or IPPROTO_TCP). The procedure dispatch has the following form:

```
dispatch(struct svc_req *request, SVCXPRT *xpvt);
```

The svc_register() routine returns one if it succeeds, and zero otherwise.

```
void svc_run(void);
```

This routine never returns. It waits for RPC requests to arrive, and calls the appropriate service procedure using svc_getreq() when one arrives. This procedure is usually waiting for a select(2) system call to return.

```
bool_t svc_sendreply(SVCXPRT *xpvt, xdrproc_t outproc, char *out);
```

Called by an RPC service's dispatch routine to send the results of a remote procedure call. The parameter xpvt is the request's associated transport handle; outproc is the XDR routine which is used to encode the results; and out is the address of the results. This routine returns one if it succeeds, zero otherwise.

```
void svc_unregister(unsigned long prognum, unsigned long versnum);
```

Remove all mapping of the double [prognum,versnum] to dispatch routines, and of the triple [prognum,versnum,*] to port number.

```
void svcerr_auth(SVCXPRT *xpvt, enum auth_stat why);
```

Called by a service dispatch routine that refuses to perform a remote procedure call due to an authentication error.

```
void svcerr_decode(SVCXPRT *xpvt);
```

Called by a service dispatch routine that cannot successfully decode its parameters. See also svc_getargs().

```
void svcerr_noproc(SVCXPRT *xpvt);
```

Called by a service dispatch routine that does not implement the procedure

number that the caller requests.

```
void svcerr_noprog(SVCXPRT *xpvt);
```

Called when the desired program is not registered with the RPC package.

Service implementors usually do not need this routine.

```
void svcerr_progvers(SVCXPRT *xpvt);
```

Called when the desired version of a program is not registered with the RPC package. Service implementors usually do not need this routine.

```
void svcerr_systemerr(SVCXPRT *xpvt);
```

Called by a service dispatch routine when it detects a system error not covered by any particular protocol. For example, if a service can no longer allocate storage, it may call this routine.

```
void svcerr_weakauth(SVCXPRT *xpvt);
```

Called by a service dispatch routine that refuses to perform a remote procedure call due to insufficient authentication parameters. The routine calls `svcerr_auth(xpvt, AUTH_TOOWEAK)`.

```
SVCXPRT *svcsfd_create(int fd, unsigned int sendsize,  
                      unsigned int recvsize);
```

Create a service on top of any open file descriptor. Typically, this file descriptor is a connected socket for a stream protocol such as TCP. `sendsize` and `recvsize` indicate sizes for the send and receive buffers. If they are zero, a reasonable default is chosen.

```
SVCXPRT *svccraw_create(void);
```

This routine creates a toy RPC service transport, to which it returns a pointer. The transport is really a buffer within the process's address space, so the corresponding RPC client should live in the same address space; see `clntraw_create()`. This routine allows simulation of RPC and acquisition of RPC overheads (such as round trip times), without any kernel interference. This routine returns NULL if it fails.

```
SVCXPRT *svctcp_create(int sock, unsigned int send_buf_size,  
                     unsigned int recv_buf_size);
```

This routine creates a TCP/IP-based RPC service transport, to which it returns a pointer. The transport is associated with the socket `sock`, which may be `RPC_ANYSOCK`, in which case a new socket is created. If the socket is

not bound to a local TCP port, then this routine binds it to an arbitrary port. Upon completion, `xprt->xp_sock` is the transport's socket descriptor, and `xprt->xp_port` is the transport's port number. This routine returns NULL if it fails. Since TCP-based RPC uses buffered I/O, users may specify the size of buffers; values of zero choose suitable defaults.

```
SVCXPRT *svcudp_bufcreate(int sock, unsigned int sendsize,  
                          unsigned int recosize);
```

This routine creates a UDP/IP-based RPC service transport, to which it returns a pointer. The transport is associated with the socket `sock`, which may be `RPC_ANYSOCK`, in which case a new socket is created. If the socket is not bound to a local UDP port, then this routine binds it to an arbitrary port. Upon completion, `xprt->xp_sock` is the transport's socket descriptor, and `xprt->xp_port` is the transport's port number. This routine returns NULL if it fails.

This allows the user to specify the maximum packet size for sending and receiving UDP-based RPC messages.

```
SVCXPRT *svcudp_create(int sock);
```

This call is equivalent to `svcudp_bufcreate(sock,SZ,SZ)` for some default size `SZ`.

```
bool_t xdr_accepted_reply(XDR *xdrs, struct accepted_reply *ar);
```

Used for encoding RPC reply messages. This routine is useful for users who wish to generate RPC-style messages without using the RPC package.

```
bool_t xdr_authunix_parms(XDR *xdrs, struct authunix_parms *aupp);
```

Used for describing UNIX credentials. This routine is useful for users who wish to generate these credentials without using the RPC authentication package.

```
void xdr_callhdr(XDR *xdrs, struct rpc_msg *chdr);
```

Used for describing RPC call header messages. This routine is useful for users who wish to generate RPC-style messages without using the RPC package.

```
bool_t xdr_callmsg(XDR *xdrs, struct rpc_msg *cmsg);
```

Used for describing RPC call messages. This routine is useful for users who wish to generate RPC-style messages without using the RPC package.

```
bool_t xdr_opaque_auth(XDR *xdrs, struct opaque_auth *ap);
```


?callrpc(), clnt_broadcast(), ? ? ?
 ?clnt_call(), clnt_destroy(), ? ? ?
 ?clnt_create(), clnt_control(), ? ? ?
 ?clnt_freeres(), clnt_geterr(), ? ? ?
 ?clnt_pcreateerror(), clnt_perrno(), ? ? ?
 ?clnt_perror(), ? ? ?
 ?clnt_spcreateerror(), ? ? ?
 ?clnt_sperno(), clnt_sperro(), ? ? ?
 ?clntraw_create(), clnttcp_create(), ? ? ?
 ?clntudp_create(), ? ? ?
 ?clntudp_bufcreate(), ? ? ?
 ?get_myaddress(), pmap_getmaps(), ? ? ?
 ?pmap_getport(), pmap_rmtcall(), ? ? ?
 ?pmap_set(), pmap_unset(), ? ? ?
 ?registerrpc(), svc_destroy(), ? ? ?
 ?svc_freeargs(), svc_getargs(), ? ? ?
 ?svc_getcaller(), svc_getreqset(), ? ? ?
 ?svc_getreq(), svc_register(), ? ? ?
 ?svc_run(), svc_sendreply(), ? ? ?
 ?svc_unregister(), svcerr_auth(), ? ? ?
 ?svcerr_decode(), svcerr_noproc(), ? ? ?
 ?svcerr_noprog(), svcerr_progvers(), ? ? ?
 ?svcerr_systemerr(), ? ? ?
 ?svcerr_weakauth(), ? ? ?
 ?svctcp_create(), svcrow_create(), ? ? ?
 ?svctcp_create(), ? ? ?
 ?svctcp_create(), ? ? ?
 ?svctcp_create(), xdr_accepted_re? ? ? ?
 ?ply(), ? ? ?
 ?xdr_authunix_parms(), ? ? ?
 ?xdr_callhdr(), ? ? ?
 ?xdr_callmsg(), xdr_opaque_auth(), ? ? ?
 ?xdr_pmap(), xdr_pmaplist(), ? ? ?

?xdr_rejected_reply(), ? ? ?
?xdr_replymsg(), ? ? ?
?xprt_register(), xprt_unregister() ? ? ?
??

SEE ALSO

xdr(3)

The following manuals:

Remote Procedure Calls: Protocol Specification

Remote Procedure Call Programming Guide

rpcgen Programming Guide

RPC: Remote Procedure Call Protocol Specification, RFC 1050, Sun Microsystems, Inc., USC-ISI.

COLOPHON

This page is part of release 5.05 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

2017-09-15

RPC(3)