



Rocky Enterprise Linux 9.2 Manual Pages on command 'xdr_char.3'

C:\>man xdr_char.3

XDR(3) Linux Programmer's Manual XDR(3)

NAME

xdr - library routines for external data representation

SYNOPSIS AND DESCRIPTION

These routines allow C programmers to describe arbitrary data structures in a machine-independent fashion. Data for remote procedure calls are transmitted using these routines.

The prototypes below are declared in <rpc/xdr.h> and make use of the following types:

```
typedef int bool_t;
typedef bool_t (*xdrproc_t) (XDR *, void *,...);
```

For the declaration of the XDR type, see <rpc/xdr.h>.

```
bool_t xdr_array(XDR *xdrs, char **arrp, unsigned int *sizep,
                unsigned int maxsize, unsigned int elsize,
                xdrproc_t elproc);
```

A filter primitive that translates between variable-length arrays and their corresponding external representations. The argument *arrp* is the address of the pointer to the array, while *sizep* is the address of the element count of the array; this element count cannot exceed *maxsize*. The argument *elsize* is the `sizeof` each of the array's elements, and *elproc* is an XDR filter that translates between the array elements' C form, and their external representation. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_bool(XDR *xdrs, bool_t *bp);
```

A filter primitive that translates between booleans (C integers) and their external representations. When encoding data, this filter produces values of either one or zero. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_bytes(XDR *xdrs, char **sp, unsigned int *sizep,  
                unsigned int maxsize);
```

A filter primitive that translates between counted byte strings and their external representations. The argument `sp` is the address of the string pointer. The length of the string is located at address `sizep`; strings can not be longer than `maxsize`. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_char(XDR *xdrs, char *cp);
```

A filter primitive that translates between C characters and their external representations. This routine returns one if it succeeds, zero otherwise.

Note: encoded characters are not packed, and occupy 4 bytes each. For arrays of characters, it is worthwhile to consider `xdr_bytes()`, `xdr_opaque()` or `xdr_string()`.

```
void xdr_destroy(XDR *xdrs);
```

A macro that invokes the destroy routine associated with the XDR stream, `xdrs`. Destruction usually involves freeing private data structures associated with the stream. Using `xdrs` after invoking `xdr_destroy()` is undefined.

```
bool_t xdr_double(XDR *xdrs, double *dp);
```

A filter primitive that translates between C double precision numbers and their external representations. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_enum(XDR *xdrs, enum_t *ep);
```

A filter primitive that translates between C enums (actually integers) and their external representations. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_float(XDR *xdrs, float *fp);
```

A filter primitive that translates between C floats and their external representations. This routine returns one if it succeeds, zero otherwise.

```
void xdr_free(xdrproc_t proc, char *objp);
```

Generic freeing routine. The first argument is the XDR routine for the object being freed. The second argument is a pointer to the object itself.

Note: the pointer passed to this routine is not freed, but what it points to is freed (recursively).

```
unsigned int xdr_getpos(XDR *xdrs);
```

A macro that invokes the get-position routine associated with the XDR stream, xdrs. The routine returns an unsigned integer, which indicates the position of the XDR byte stream. A desirable feature of XDR streams is that simple arithmetic works with this number, although the XDR stream instances need not guarantee this.

```
long *xdr_inline(XDR *xdrs, int len);
```

A macro that invokes the inline routine associated with the XDR stream, xdrs. The routine returns a pointer to a contiguous piece of the stream's buffer; len is the byte length of the desired buffer. Note: pointer is cast to long *.

Warning: xdr_inline() may return NULL (0) if it cannot allocate a contiguous piece of a buffer. Therefore the behavior may vary among stream instances; it exists for the sake of efficiency.

```
bool_t xdr_int(XDR *xdrs, int *ip);
```

A filter primitive that translates between C integers and their external representations. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_long(XDR *xdrs, long *lp);
```

A filter primitive that translates between C long integers and their external representations. This routine returns one if it succeeds, zero otherwise.

```
void xdrmem_create(XDR *xdrs, char *addr, unsigned int size,  
                  enum xdr_op op);
```

This routine initializes the XDR stream object pointed to by xdrs. The stream's data is written to, or read from, a chunk of memory at location addr whose length is no more than size bytes long. The op determines the direction of the XDR stream (either XDR_ENCODE, XDR_DECODE, or XDR_FREE).

```
bool_t xdr_opaque(XDR *xdrs, char *cp, unsigned int cnt);
```

A filter primitive that translates between fixed size opaque data and its external representation. The argument `cp` is the address of the opaque object, and `cnt` is its size in bytes. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_pointer(XDR *xdrs, char **objpp,  
                  unsigned int objsize, xdrproc_t xdrobj);
```

Like `xdr_reference()` except that it serializes null pointers, whereas `xdr_reference()` does not. Thus, `xdr_pointer()` can represent recursive data structures, such as binary trees or linked lists.

```
void xdrrec_create(XDR *xdrs, unsigned int sendsize,  
                  unsigned int recvsize, char *handle,  
                  int (*readit) (char *, char *, int),  
                  int (*writeit) (char *, char *, int));
```

This routine initializes the XDR stream object pointed to by `xdrs`. The stream's data is written to a buffer of size `sendsize`; a value of zero indicates the system should use a suitable default. The stream's data is read from a buffer of size `recvsize`; it too can be set to a suitable default by passing a zero value. When a stream's output buffer is full, `writeit` is called. Similarly, when a stream's input buffer is empty, `readit` is called.

The behavior of these two routines is similar to the system calls `read(2)` and `write(2)`, except that `handle` is passed to the former routines as the first argument. Note: the XDR stream's `op` field must be set by the caller.

Warning: to read from an XDR stream created by this API, you'll need to call `xdrrec_skiprecord()` first before calling any other XDR APIs. This inserts additional bytes in the stream to provide record boundary information.

Also, XDR streams created with different `xdr*_create` APIs are not compatible for the same reason.

```
bool_t xdrrec_endofrecord(XDR *xdrs, int sendnow);
```

This routine can be invoked only on streams created by `xdrrec_create()`. The data in the output buffer is marked as a completed record, and the output buffer is optionally written out if `sendnow` is nonzero. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdrrec_eof(XDR *xdrs);
```

This routine can be invoked only on streams created by `xdrrec_create()`. After consuming the rest of the current record in the stream, this routine returns one if the stream has no more input, zero otherwise.

```
bool_t xdrrec_skiprecord(XDR *xdrs);
```

This routine can be invoked only on streams created by `xdrrec_create()`. It tells the XDR implementation that the rest of the current record in the stream's input buffer should be discarded. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_reference(XDR *xdrs, char **pp, unsigned int size,  
                    xdrproc_t proc);
```

A primitive that provides pointer chasing within structures. The argument `pp` is the address of the pointer; `size` is the `sizeof` the structure that `*pp` points to; and `proc` is an XDR procedure that filters the structure between its C form and its external representation. This routine returns one if it succeeds, zero otherwise.

Warning: this routine does not understand null pointers. Use `xdr_pointer()` instead.

```
xdr_setpos(XDR *xdrs, unsigned int pos);
```

A macro that invokes the set position routine associated with the XDR stream `xdrs`. The argument `pos` is a position value obtained from `xdr_getpos()`. This routine returns one if the XDR stream could be repositioned, and zero otherwise.

Warning: it is difficult to reposition some types of XDR streams, so this routine may fail with one type of stream and succeed with another.

```
bool_t xdr_short(XDR *xdrs, short *sp);
```

A filter primitive that translates between C short integers and their external representations. This routine returns one if it succeeds, zero otherwise.

```
void xdrstdio_create(XDR *xdrs, FILE *file, enum xdr_op op);
```

This routine initializes the XDR stream object pointed to by `xdrs`. The XDR stream data is written to, or read from, the stdio stream file. The argument `op` determines the direction of the XDR stream (either `XDR_ENCODE`, `XDR_DECODE`, or `XDR_FREE`).

Warning: the destroy routine associated with such XDR streams calls `fflush(3)` on the file stream, but never `fclose(3)`.

```
bool_t xdr_string(XDR *xdrs, char **sp, unsigned int maxsize);
```

A filter primitive that translates between C strings and their corresponding external representations. Strings cannot be longer than `maxsize`. Note: `sp` is the address of the string's pointer. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_u_char(XDR *xdrs, unsigned char *ucp);
```

A filter primitive that translates between unsigned C characters and their external representations. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_u_int(XDR *xdrs, unsigned *up);
```

A filter primitive that translates between C unsigned integers and their external representations. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_u_long(XDR *xdrs, unsigned long *ulp);
```

A filter primitive that translates between C unsigned long integers and their external representations. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_u_short(XDR *xdrs, unsigned short *usp);
```

A filter primitive that translates between C unsigned short integers and their external representations. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_union(XDR *xdrs, int *dscmp, char *unp,
```

```
    struct xdr_discrim *choices,  
    xdrproc_t defaultarm); /* may equal NULL */
```

A filter primitive that translates between a discriminated C union and its corresponding external representation. It first translates the discriminant of the union located at `dscmp`. This discriminant is always an `enum_t`. Next the union located at `unp` is translated. The argument `choices` is a pointer to an array of `xdr_discrim()` structures. Each structure contains an ordered pair of `[value,proc]`. If the union's discriminant is equal to the associated value, then the `proc` is called to translate the union. The end of the

xdr_discrim() structure array is denoted by a routine of value NULL. If the discriminant is not found in the choices array, then the default routine is called (if it is not NULL). Returns one if it succeeds, zero otherwise.

```
bool_t xdr_vector(XDR *xdrs, char *arrp, unsigned int size,
                 unsigned int elsize, xdrproc_t elproc);
```

A filter primitive that translates between fixed-length arrays and their corresponding external representations. The argument arrp is the address of the pointer to the array, while size is the element count of the array. The argument elsize is the sizeof each of the array's elements, and elproc is an XDR filter that translates between the array elements' C form, and their external representation. This routine returns one if it succeeds, zero otherwise.

```
bool_t xdr_void(void);
```

This routine always returns one. It may be passed to RPC routines that require a function argument, where nothing is to be done.

```
bool_t xdr_wrapstring(XDR *xdrs, char **sp);
```

A primitive that calls xdr_string(xdrs, sp, MAXUN.SIGNED); where MAXUN.SIGNED is the maximum value of an unsigned integer. xdr_wrapstring() is handy because the RPC package passes a maximum of two XDR routines as arguments, and xdr_string(), one of the most frequently used primitives, requires three. Returns one if it succeeds, zero otherwise.

ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

??

?Interface	? Attribute	? Value	?
------------	-------------	---------	---

??

?xdr_array(), xdr_bool(),	? Thread safety	? MT-Safe	?
---------------------------	-----------------	-----------	---

?xdr_bytes(), xdr_char(),	?	?	?
---------------------------	---	---	---

?xdr_destroy(), xdr_double(),	?	?	?
-------------------------------	---	---	---

?xdr_enum(), xdr_float(),	?	?	?
---------------------------	---	---	---

?xdr_free(), xdr_getpos(),	?	?	?
----------------------------	---	---	---

?xdr_inline(), xdr_int(),	?	?	?
---------------------------	---	---	---

?xdr_long(), xdrmem_create(), ? ? ?
 ?xdr_opaque(), xdr_pointer(), ? ? ?
 ?xdrrec_create(), xdrrec_eof(), ? ? ?
 ?xdrrec_endofrecord(), ? ? ?
 ?xdrrec_skiprecord(), ? ? ?
 ?xdr_reference(), xdr_setpos(), ? ? ?
 ?xdr_short(), xdrstdio_create(), ? ? ?
 ?xdr_string(), xdr_u_char(), ? ? ?
 ?xdr_u_int(), xdr_u_long(), ? ? ?
 ?xdr_u_short(), xdr_union(), ? ? ?
 ?xdr_vector(), xdr_void(), ? ? ?
 ?xdr_wrapstring() ? ? ?
 ???

SEE ALSO

rpc(3)

The following manuals:

eXternal Data Representation Standard: Protocol Specification

eXternal Data Representation: Sun Technical Notes

XDR: External Data Representation Standard, RFC 1014, Sun Microsystems, Inc., USC-ISI.

COLOPHON

This page is part of release 5.05 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.