



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'EVP RAND-TEST-RAND.7ossl' command

\$ man EVP RAND-TEST-RAND.7ossl

EVP RAND-TEST-RAND(7ossl) OpenSSL EVP RAND-TEST-RAND(7ossl)

NAME

EVP RAND-TEST-RAND - The test EVP RAND implementation

DESCRIPTION

Support for a test generator through the EVP RAND API. This generator is for test purposes only, it does not generate random numbers.

Identity

"TEST-RAND" is the name for this implementation; it can be used with the EVP RAND_fetch() function.

Supported parameters

The supported parameters are:

"state" (OSSL RAND_PARAM_STATE) <integer>

These parameter works as described in "PARAMETERS" in EVP RAND(3).

"strength" (OSSL RAND_PARAM_STRENGTH) <unsigned integer>

"reseed_requests" (OSSL DRBG_PARAM_RESEED_REQUESTS) <unsigned integer>

"reseed_time_interval" (OSSL DRBG_PARAM_RESEED_TIME_INTERVAL) <integer>

"max_request" (OSSL DRBG_PARAM_RESEED_REQUESTS) <unsigned integer>

"min_entropylen" (OSSL_DRBG_PARAM_MIN_ENTROPYLEN) <unsigned integer>
"max_entropylen" (OSSL_DRBG_PARAM_MAX_ENTROPYLEN) <unsigned integer>
"min_noncelen" (OSSL_DRBG_PARAM_MIN_NONCELEN) <unsigned integer>
"max_noncelen" (OSSL_DRBG_PARAM_MAX_NONCELEN) <unsigned integer>
"max_perslen" (OSSL_DRBG_PARAM_MAX_PERSLEN) <unsigned integer>
"max_adinlen" (OSSL_DRBG_PARAM_MAX_ADINLEN) <unsigned integer>
"reseed_counter" (OSSL_DRBG_PARAM_RESEED_COUNTER) <unsigned integer>

These parameters work as described in "PARAMETERS" in EVP_RAND(3),
except that they can all be set as well as read.

"test_entropy" (OSSL_RAND_PARAM_TEST_ENTROPY) <octet string>

Sets the bytes returned when the test generator is sent an entropy
request. The current position is remembered across generate calls.
If there are insufficient data present to satisfy a call, an error
is returned.

"test_nonce" (OSSL_RAND_PARAM_TEST_NONCE) <octet string>

Sets the bytes returned when the test generator is sent a nonce
request. Each nonce request will return all of the bytes.

NOTES

A context for a test generator can be obtained by calling:

```
EVP_RAND *rand = EVP_RAND_fetch(NULL, "TEST-RAND", NULL);  
EVP_RAND_CTX *rctx = EVP_RAND_CTX_new(rand);
```

EXAMPLES

```
EVP_RAND *rand;  
EVP_RAND_CTX *rctx;  
unsigned char bytes[100];  
OSSL_PARAM params[4], *p = params;  
unsigned char entropy[1000] = { ... };  
unsigned char nonce[20] = { ... };
```

```
unsigned int strength = 48;

rand = EVP RAND fetch(NULL, "TEST-RAND", NULL);
rctx = EVP RAND CTX new(rand, NULL);
EVP RAND free(rand);

*p++ = OSSL_PARAM_construct_uint(OSSL_PARAM_STRENGTH, &strength);
*p++ = OSSL_PARAM_construct_octet_string(OSSL_PARAM_TEST_ENTROPY,
entropy, sizeof(entropy));
*p++ = OSSL_PARAM_construct_octet_string(OSSL_PARAM_TEST_NONCE,
nonce, sizeof(nonce));
*p = OSSL_PARAM_construct_end();
EVP RAND instantiate(rctx, strength, 0, NULL, 0, params);

EVP RAND generate(rctx, bytes, sizeof(bytes), strength, 0, NULL, 0);

EVP RAND CTX free(rctx);
```

SEE ALSO

EVP RAND(3), "PARAMETERS" in EVP RAND(3)

COPYRIGHT

Copyright 2020-2021 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.