



Rocky Enterprise Linux 9.2 Manual Pages on command 'SSL_new.3ossl'

\$ man SSL_new.3ossl

SSL_NEW(3ossl) OpenSSL SSL_NEW(3ossl)

NAME

SSL_dup, SSL_new, SSL_up_ref - create an SSL structure for a connection

SYNOPSIS

```
#include <openssl/ssl.h>
```

```
SSL *SSL_dup(SSL *s);
```

```
SSL *SSL_new(SSL_CTX *ctx);
```

```
int SSL_up_ref(SSL *s);
```

DESCRIPTION

SSL_new() creates a new SSL structure which is needed to hold the data for a TLS/SSL connection. The new structure inherits the settings of the underlying context ctx: connection method, options, verification settings, timeout settings. An SSL structure is reference counted.

Creating an SSL structure for the first time increments the reference

count. Freeing it (using `SSL_free`) decrements it. When the reference count drops to zero, any memory or resources allocated to the SSL structure are freed.

`SSL_up_ref()` increments the reference count for an existing SSL structure.

The function `SSL_dup()` creates and returns a new SSL structure from the same `SSL_CTX` that was used to create `s`. It additionally duplicates a subset of the settings in `s` into the new SSL object.

For `SSL_dup()` to work, the connection **MUST** be in its initial state and **MUST NOT** have yet started the SSL handshake. For connections that are not in their initial state `SSL_dup()` just increments an internal reference count and returns the same handle. It may be possible to use `SSL_clear(3)` to recycle an SSL handle that is not in its initial state for re-use, but this is best avoided. Instead, save and restore the session, if desired, and construct a fresh handle for each connection.

The subset of settings in `s` that are duplicated are:

- any session data if configured (including the `session_id_context`)
- any `tmp_dh` settings set via `SSL_set_tmp_dh(3)`,
`SSL_set_tmp_dh_callback(3)`, or `SSL_set_dh_auto(3)`
- any configured certificates, private keys or certificate chains
- any configured signature algorithms, or client signature algorithms
- any DANE settings
- any Options set via `SSL_set_options(3)`
- any Mode set via `SSL_set_mode(3)`
- any minimum or maximum protocol settings set via
`SSL_set_min_proto_version(3)` or `SSL_set_max_proto_version(3)` (Note:
Only from OpenSSL 1.1.1h and above)
- any verify mode, callback or depth set via `SSL_set_verify(3)` or

SSL_set_verify_depth(3) or any configured X509 verification parameters
any msg callback or info callback set via SSL_set_msg_callback(3) or
SSL_set_info_callback(3)
any default password callback set via SSL_set_default_passwd_cb(3)
any session id generation callback set via
SSL_set_generate_session_id(3)
any configured Cipher List
initial accept (server) or connect (client) state
the max cert list value set via SSL_set_max_cert_list(3)
the read_ahead value set via SSL_set_read_ahead(3)
application specific data set via SSL_set_ex_data(3)
any CA list or client CA list set via SSL_set0_CA_list(3),
SSL_set0_client_CA_list() or similar functions
any security level settings or callbacks
any configured serverinfo data
any configured PSK identity hint
any configured custom extensions
any client certificate types configured via
SSL_set1_client_certificate_types

RETURN VALUES

The following return values can occur:

NULL

The creation of a new SSL structure failed. Check the error stack to find out the reason.

Pointer to an SSL structure

The return value points to an allocated SSL structure.

SSL_up_ref() returns 1 for success and 0 for failure.

SSL_free(3), SSL_clear(3), SSL_CTX_set_options(3), SSL_get_SSL_CTX(3),
ssl(7)

COPYRIGHT

Copyright 2000-2021 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use
this file except in compliance with the License. You can obtain a copy
in the file LICENSE in the source distribution or at
<<https://www.openssl.org/source/license.html>>.

3.0.7 2023-07-13 SSL_NEW(3ossl)