



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'setvbuf.3'

\$ man setvbuf.3

SETBUF(3) Linux Programmer's Manual SETBUF(3)

NAME

`setbuf`, `setbuffer`, `setlinebuf`, `setvbuf` - stream buffering operations

SYNOPSIS

```
#include <stdio.h>

void setbuf(FILE *stream, char *buf);

void setbuffer(FILE *stream, char *buf, size_t size);

void setlinebuf(FILE *stream);

int setvbuf(FILE *stream, char *buf, int mode, size_t size);
```

Feature Test Macro Requirements for glibc (see `feature_test_macros(7)`):

setbuffer(), setlinebuf():

Since glibc 2.19:

DEFAULT SOURCE

Glibc 2.19 and earlier:

BSD SOURCE

DESCRIPTION

The three types of buffering available are unbuffered, block buffered,

and line buffered. When an output stream is unbuffered, information

appears on the destination file or terminal as soon as written; when it is block buffered many characters are saved up and written as a block; when it is line buffered characters are saved up until a newline is output or input is read from any stream attached to a terminal device (typically stdin). The function fflush(3) may be used to force the block out early. (See fclose(3).)

Normally all files are block buffered. If a stream refers to a terminal (as stdout normally does), it is line buffered. The standard error stream stderr is always unbuffered by default.

The setvbuf() function may be used on any open stream to change its buffer. The mode argument must be one of the following three macros:

`_IONBF` unbuffered

`_IOLBF` line buffered

`_IOFBF` fully buffered

Except for unbuffered files, the buf argument should point to a buffer at least size bytes long; this buffer will be used instead of the current buffer. If the argument buf is NULL, only the mode is affected; a new buffer will be allocated on the next read or write operation. The setvbuf() function may be used only after opening a stream and before any other operations have been performed on it.

The other three calls are, in effect, simply aliases for calls to setvbuf(). The setbuf() function is exactly equivalent to the call

```
setvbuf(stream, buf, buf ? _IOFBF : _IONBF, BUFSIZ);
```

The setbuffer() function is the same, except that the size of the buffer is up to the caller, rather than being determined by the default BUFSIZ. The setlinebuf() function is exactly equivalent to the call:

```
setvbuf(stream, NULL, _IOLBF, 0);
```

RETURN VALUE

The function setvbuf() returns 0 on success. It returns nonzero on failure (mode is invalid or the request cannot be honored). It may set errno on failure.

The other functions do not return a value.

For an explanation of the terms used in this section, see at?

tributes(7).

??

?Interface ? Attribute ? Value ?

??

?setbuf(), setbuffer(), ? Thread safety ? MT-Safe ?

?setlinebuf(), setvbuf() ? ? ?

??

CONFORMING TO

The setbuf() and setvbuf() functions conform to C89 and C99.

BUGS

You must make sure that the space that buf points to still exists by the time stream is closed, which also happens at program termination.

For example, the following is invalid:

```
#include <stdio.h>

int
main(void)
{
    char buf[BUFSIZ];
    setbuf(stdin, buf);
    printf("Hello, world!\n");
    return 0;
}
```

SEE ALSO

stdbuf(1), fclose(3), fflush(3), fopen(3), fread(3), malloc(3),

printf(3), puts(3)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.