



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'rpcsec_gss.3t'

\$ man rpcsec_gss.3t

RPC_GSS_SECCREATE(3) BSD Library Functions Manual RPC_GSS_SECCREATE(3)

NAME

RPCSEC_GSS ? GSS-API based authentication for RPC

SYNOPSIS

```
#include <rpc/rpcsec_gss.h>
```

DESCRIPTION

RPCSEC_GSS is a security mechanism for the RPC protocol. It uses the Generic Security Service API (GSS-API) to establish a security context between a client and a server and to ensure that all subsequent communication between client and server are properly authenticated. Optionally, extra protection can be applied to the connection. The integrity service uses checksums to ensure that all data sent by a peer is received without modification. The privacy service uses encryption to ensure that no third party can access the data for a connection.

To use this system, an application must first use `rpc_gss_seccreate()` to establish a security context.

DATA STRUCTURES

Data structures used by RPCSEC_GSS appear below.

`rpc_gss_service_t`

This type defines the types of security service required for `rpc_gss_seccreate()`.

```
typedef enum {  
    rpc_gss_svc_default    = 0,  
    rpc_gss_svc_none       = 1,  
    rpc_gss_svc_integrity  = 2,
```

```
    rpc_gss_svc_privacy    = 3
```

```
    } rpc_gss_service_t;
```

```
rpc_gss_options_req_t
```

This structure contains various optional values which are used while creating a security context.

```
typedef struct {
    int        req_flags;    /* GSS request bits */
    int        time_req;    /* requested lifetime */
    gss_cred_id_t  my_cred;  /* GSS credential */
    gss_channel_bindings_t input_channel_bindings;
} rpc_gss_options_req_t;
```

```
rpc_gss_options_ret_t
```

Various details of the created security context are returned using this structure.

```
typedef struct {
    int        major_status;
    int        minor_status;
    u_int      rpcsec_version;
    int        ret_flags;
    int        time_req;
    gss_ctx_id_t  gss_context;
    char        actual_mechanism[MAX_GSS_MECH];
} rpc_gss_options_ret_t;
```

```
rpc_gss_principal_t
```

This type is used to refer to an client principal which is represented in GSS-API exported name form (see `gss_export_name(3)` for more details). Names in this format may be stored in access control lists or compared with other names in exported name form.

This structure is returned by `rpc_gss_get_principal_name()` and is also referenced by the `rpc_gss_rawcred_t` structure.

```
typedef struct {
    int        len;
    char        name[1];
} *rpc_gss_principal_t;
```

```
rpc_gss_rawcred_t
```

This structure is used to access the raw credentials associated with a security con?

text.

```
typedef struct {
    u_int    version;    /* RPC version number */
    const char *mechanism; /* security mechanism */
    const char *qop;     /* quality of protection */
    rpc_gss_principal_t client_principal; /* client name */
    const char *svc_principal; /* server name */
    rpc_gss_service_t service; /* service type */
} rpc_gss_rawcred_t;
```

rpc_gss_ucred_t

Unix credentials which are derived from the raw credentials, accessed via

rpc_gss_getcred().

```
typedef struct {
    uid_t    uid;        /* user ID */
    gid_t    gid;        /* group ID */
    short    gidlen;
    gid_t    *gidlist; /* list of groups */
} rpc_gss_ucred_t;
```

rpc_gss_lock_t

Structure used to enforce a particular QOP and service.

```
typedef struct {
    bool_t    locked;
    rpc_gss_rawcred_t *raw_cred;
} rpc_gss_lock_t;
```

rpc_gss_callback_t

Callback structure used by rpc_gss_set_callback().

```
typedef struct {
    u_int    program;    /* RPC program number */
    u_int    version;    /* RPC version number */
    /* user defined callback */
    bool_t    (*callback)(struct svc_req *req,
                          gss_cred_id_t deleg,
```

```

        gss_ctx_id_t gss_context,
        rpc_gss_lock_t *lock,
        void **cookie);
} rpc_gss_callback_t;
rpc_gss_error_t
Structure used to return error information by rpc_gss_get_error().
typedef struct {
    int    rpc_gss_error;
    int    system_error; /* same as errno */
} rpc_gss_error_t;
/*
 * Values for rpc_gss_error
 */
#define RPC_GSS_ER_SUCCESS    0    /* no error */
#define RPC_GSS_ER_SYSTEMERROR 1    /* system error */

```

INDEX

rpc_gss_seccreate(3)

Create a new security context

rpc_gss_set_defaults(3)

Set service and quality of protection for a context

rpc_gss_max_data_length(3)

Calculate maximum client message sizes.

rpc_gss_get_error(3)

Get details of the last error

rpc_gss_mech_to_oid(3)

Convert a mechanism name to the corresponding GSS-API oid.

rpc_gss_oid_to_mech(3)

Convert a GSS-API oid to a mechanism name

rpc_gss_qop_to_num(3)

Convert a quality of protection name to the corresponding number

rpc_gss_get_mechanisms(3)

Get a list of security mechanisms.

rpc_gss_get_mech_info(3)

Return extra information about a security mechanism

`rpc_gss_get_versions(3)`

Return the maximum and minimum supported versions of the RPCSEC_GSS protocol

`rpc_gss_is_installed(3)`

Query for the presence of a particular security mechanism

`rpc_gss_set_svc_name(3)`

Set the name of a service principal which matches a given RPC program plus version pair

`rpc_gss_getcred(3)`

Get credential details for the security context of an RPC request

`rpc_gss_set_callback(3)`

Install a callback routine which is called on the server when new security contexts are created

`rpc_gss_get_principal_name(3)`

Create a client principal name from various strings

`rpc_gss_svc_max_data_length(3)`

Calculate maximum server message sizes.

AVAILABILITY

These functions are part of `libtirpc`.

SEE ALSO

`rpc(3)`, `gssapi(3)`

AUTHORS

This manual page was written by Doug Rabson <dfr@FreeBSD.org>.

BSD

January 26, 2010

BSD