

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'setpwent.3'

## \$ man setpwent.3

GETPWENT(3)

Linux Programmer's Manual

GETPWENT(3)

NAME

getpwent, setpwent, endpwent - get password file entry

### **SYNOPSIS**

#include <sys/types.h>

#include <pwd.h>

struct passwd \*getpwent(void);

void setpwent(void);

void endpwent(void);

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

getpwent(), setpwent(), endpwent():

\_XOPEN\_SOURCE >= 500

|| /\* Glibc since 2.19: \*/ \_DEFAULT\_SOURCE

|| /\* Glibc versions <= 2.19: \*/ \_BSD\_SOURCE || \_SVID\_SOURCE

### **DESCRIPTION**

The getpwent() function returns a pointer to a structure containing the broken-out fields of a record from the password database (e.g., the local password file /etc/passwd, NIS, and LDAP). The first time getpwent() is called, it returns the first entry; thereafter, it returns successive entries.

The setpwent() function rewinds to the beginning of the password database.

The endpwent() function is used to close the password database after all processing has been performed.

The passwd structure is defined in <pwd.h> as follows:

```
struct passwd {
  char *pw_name; /* username */
  char *pw_passwd; /* user password */
  uid_t pw_uid; /* user ID */
  gid_t pw_gid; /* group ID */
  char *pw_gecos; /* user information */
  char *pw_dir; /* home directory */
  char *pw_shell; /* shell program */
};
```

When shadow(5) passwords are enabled (which is default on many GNU/Linux installations) the content of pw\_passwd is usually not very useful. In such a case most passwords are stored in a separate file.

The variable pw\_shell may be empty, in which case the system will execute the default shell (/bin/sh) for the user.

For more information about the fields of this structure, see passwd(5).

## **RETURN VALUE**

The getpwent() function returns a pointer to a passwd structure, or NULL if there are no more entries or an error occurred. If an error occurs, error is set appropriately. If one wants to check error after the call, it should be set to zero before the call.

The return value may point to a static area, and may be overwritten by subsequent calls to getpwent(), getpwnam(3), or getpwuid(3). (Do not pass the returned pointer to free(3).)

## **ERRORS**

EINTR A signal was caught; see signal(7).

EIO I/O error.

EMFILE The per-process limit on the number of open file descriptors has been reached.

ENFILE The system-wide limit on the total number of open files has been reached.

ENOMEM Insufficient memory to allocate passwd structure.

ERANGE Insufficient buffer space supplied.

## **FILES**

/etc/passwd

local password database file

## **ATTRIBUTES**

For an explanation of the terms used in this section, see attributes(7).

?Interface ? Attribute ? Value ?getpwent() ? Thread safety ? MT-Unsafe race:pwent ? ? race:pwentbuf locale ?setpwent(), ? Thread safety ? MT-Unsafe race:pwent locale ? ? ? ?endpwent() ? In the above table, pwent in race:pwent signifies that if any of the functions setpwent(), getpwent(), or endpwent() are used in parallel in different threads of a program, then data races could occur. **CONFORMING TO** POSIX.1-2001, POSIX.1-2008, SVr4, 4.3BSD. The pw\_gecos field is not specified in POSIX, but is present on most implementations. SEE ALSO

fgetpwent(3), getpw(3), getpwent\_r(3), getpwnam(3), getpwuid(3), putpwent(3), shadow(5), passwd(5)

#### COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

**GNU** 2017-09-15 GETPWENT(3)