



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'strtod.3'***

**\$ man strtod.3**

STRTOD(3)

Linux Programmer's Manual

STRTOD(3)

#### **NAME**

strtod, strtod, strtold - convert ASCII string to floating-point number

#### **SYNOPSIS**

```
#include <stdlib.h>

double strtod(const char *nptr, char **endptr);

float strtodf(const char *nptr, char **endptr);

long double strtold(const char *nptr, char **endptr);
```

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

```
strtodf(), strtold():

_ISOC99_SOURCE || _POSIX_C_SOURCE >= 200112L
```

#### **DESCRIPTION**

The `strtod()`, `strtodf()`, and `strtold()` functions convert the initial portion of the string pointed to by `nptr` to double, float, and long double representation, respectively.

The expected form of the (initial portion of the) string is optional leading white space as recognized by `isspace(3)`, an optional plus ('+') or minus sign ('-') and then either (i) a decimal number, or (ii) a hexadecimal number, or (iii) an infinity, or (iv) a NAN (not-a-number).

A decimal number consists of a nonempty sequence of decimal digits possibly containing a radix character (decimal point, locale-dependent, usually '.'), optionally followed by a decimal exponent. A decimal exponent consists of an 'E' or 'e', followed by an optional plus or minus sign, followed by a nonempty sequence of decimal digits, and indicates multiplication by a power of 10.

A hexadecimal number consists of a "0x" or "0X" followed by a nonempty sequence of hexadecimal digits possibly containing a radix character, optionally followed by a binary exponent. A binary exponent consists of a 'P' or 'p', followed by an optional plus or minus sign, followed by a nonempty sequence of decimal digits, and indicates multiplication by a power of 2. At least one of radix character and binary exponent must be present.

An infinity is either "INF" or "INFINITY", disregarding case.

A NAN is "NAN" (disregarding case) optionally followed by a string, (n-char-sequence), where n-char-sequence specifies in an implementation-dependent way the type of NAN (see NOTES).

## RETURN VALUE

These functions return the converted value, if any.

If `endptr` is not `NULL`, a pointer to the character after the last character used in the conversion is stored in the location referenced by `endptr`.

If no conversion is performed, zero is returned and (unless `endptr` is null) the value of `nptr` is stored in the location referenced by `endptr`.

If the correct value would cause overflow, plus or minus `HUGE_VAL`, `HUGE_VALF`, or `HUGE_VALL` is returned (according to the return type and sign of the value), and `ERANGE` is stored in `errno`.

If the correct value would cause underflow, a value with magnitude no larger than DBL\_MIN, FLT\_MIN, or LDBL\_MIN is returned and ERANGE is stored in errno.

## ERRORS

ERANGE Overflow or underflow occurred.

## ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

?Interface      ? Attribute      ? Value      ?

?strtod(), strtodf(), strtold() ? Thread safety ? MT-Safe locale ?

## CONFORMING TO

POSIX.1-2001, POSIX.1-2008, C99

`strtod()` was also described in C89.

## NOTES

Since 0 can legitimately be returned on both success and failure, the calling program should set `errno` to 0 before the call, and then determine if an error occurred by checking whether `errno` has a nonzero value after the call.

In the glibc implementation, the n-char-sequence that optionally follows "NAN" is interpreted as an integer number (with an optional '0' or '0x' prefix to select base 8 or 16) that is to be placed in the mantissa component of the returned value.

## EXAMPLES

See the example on the `strtol(3)` manual page; the use of the functions described in this manual page is similar.

## SEE ALSO

`atof(3)`, `atoi(3)`, `atol(3)`, `nan(3)`, `nanf(3)`, `nanl(3)`, `strfromd(3)`, `strtol(3)`, `strtoul(3)`

## COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.