



## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'initrd.4'***

**C:\>man initrd.4**

INITRD(4)                      Linux Programmer's Manual                      INITRD(4)

### NAME

initrd - boot loader initialized RAM disk

### CONFIGURATION

`/dev/initrd` is a read-only block device assigned major number 1 and minor number 250. Typically `/dev/initrd` is owned by `root:disk` with mode `0400` (read access by root only). If the Linux system does not have `/dev/initrd` already created, it can be created with the following commands:

```
mknod -m 400 /dev/initrd b 1 250
```

```
chown root:disk /dev/initrd
```

Also, support for both "RAM disk" and "Initial RAM disk" (e.g., `CONFIG_BLK_DEV_RAM=y` and `CONFIG_BLK_DEV_INITRD=y`) must be compiled directly into the Linux kernel to use `/dev/initrd`. When using `/dev/initrd`, the RAM disk driver can not be loaded as a module.

### DESCRIPTION

The special file `/dev/initrd` is a read-only block device. This device is a RAM disk that is initialized (e.g., loaded) by the boot loader before the kernel is started. The kernel then can use `/dev/initrd`'s contents for a two-phase system boot-up.

In the first boot-up phase, the kernel starts up and mounts an initial root filesystem from the contents of `/dev/initrd` (e.g., RAM disk initialized by the boot loader). In the second phase, additional drivers or other modules are loaded from

the initial root device's contents. After loading the additional modules, a new root filesystem (i.e., the normal root filesystem) is mounted from a different device.

## Boot-up operation

When booting up with `initrd`, the system boots as follows:

1. The boot loader loads the kernel program and `/dev/initrd`'s contents into memory.
2. On kernel startup, the kernel uncompresses and copies the contents of the device `/dev/initrd` onto device `/dev/ram0` and then frees the memory used by `/dev/initrd`.
3. The kernel then read-write mounts the device `/dev/ram0` as the initial root filesystem.
4. If the indicated normal root filesystem is also the initial root filesystem (e.g., `/dev/ram0`) then the kernel skips to the last step for the usual boot sequence.
5. If the executable file `/linuxrc` is present in the initial root filesystem, `/linuxrc` is executed with UID 0. (The file `/linuxrc` must have executable permission. The file `/linuxrc` can be any valid executable, including a shell script.)
6. If `/linuxrc` is not executed or when `/linuxrc` terminates, the normal root filesystem is mounted. (If `/linuxrc` exits with any filesystems mounted on the initial root filesystem, then the behavior of the kernel is UNSPECIFIED. See the NOTES section for the current kernel behavior.)
7. If the normal root filesystem has a directory `/initrd`, the device `/dev/ram0` is moved from `/` to `/initrd`. Otherwise, if the directory `/initrd` does not exist, the device `/dev/ram0` is unmounted. (When moved from `/` to `/initrd`, `/dev/ram0` is not unmounted and therefore processes can remain running from `/dev/ram0`. If directory `/initrd` does not exist on the normal root filesystem and any processes remain running from `/dev/ram0` when `/linuxrc` exits, the behavior of the kernel is UNSPECIFIED. See the NOTES section for the current kernel behavior.)
8. The usual boot sequence (e.g., invocation of `/sbin/init`) is performed on the normal root filesystem.

## Options

The following boot loader options, when used with `initrd`, affect the kernel's boot-up operation:

`initrd=filename`

Specifies the file to load as the contents of `/dev/initrd`. For LOADLIN this is a command-line option. For LILO you have to use this command in the LILO configuration file `/etc/lilo.config`. The filename specified with this option will typically be a gzipped filesystem image.

#### `noinitrd`

This boot option disables the two-phase boot-up operation. The kernel performs the usual boot sequence as if `/dev/initrd` was not initialized. With this option, any contents of `/dev/initrd` loaded into memory by the boot loader contents are preserved. This option permits the contents of `/dev/initrd` to be any data and need not be limited to a filesystem image. However, device `/dev/initrd` is read-only and can be read only one time after system startup.

#### `root=device-name`

Specifies the device to be used as the normal root filesystem. For LOADLIN this is a command-line option. For LILO this is a boot time option or can be used as an option line in the LILO configuration file `/etc/lilo.config`. The device specified by the this option must be a mountable device having a suitable root filesystem.

### Changing the normal root filesystem

By default, the kernel's settings (e.g., set in the kernel file with `rdev(8)` or compiled into the kernel file), or the boot loader option setting is used for the normal root filesystems. For an NFS-mounted normal root filesystem, one has to use the `nfs_root_name` and `nfs_root_addr` boot options to give the NFS settings. For more information on NFS-mounted root see the kernel documentation file `Documentation/filesystems/nfs/nfsroot.txt` (or `Documentation/filesystems/nfsroot.txt` before Linux 2.6.33). For more information on setting the root filesystem see also the LILO and LOADLIN documentation.

It is also possible for the `/linuxrc` executable to change the normal root device. For `/linuxrc` to change the normal root device, `/proc` must be mounted. After mounting `/proc`, `/linuxrc` changes the normal root device by writing into the `proc` files `/proc/sys/kernel/real-root-dev`, `/proc/sys/kernel/nfs-root-name`, and `/proc/sys/kernel/nfs-root-addr`. For a physical root device, the root device is changed by having `/linuxrc` write the new root filesystem device number into `/proc/sys/kernel/`

nel/real-root-dev. For an NFS root filesystem, the root device is changed by having `/linuxrc` write the NFS setting into files `/proc/sys/kernel/nfs-root-name` and `/proc/sys/kernel/nfs-root-addr` and then writing 0xff (e.g., the pseudo-NFS-device number) into file `/proc/sys/kernel/real-root-dev`. For example, the following shell command line would change the normal root device to `/dev/hdb1`:

```
echo 0x365 >/proc/sys/kernel/real-root-dev
```

For an NFS example, the following shell command lines would change the normal root device to the NFS directory `/var/nfsroot` on a local networked NFS server with IP number 193.8.232.7 for a system with IP number 193.8.232.2 and named "idefix":

```
echo /var/nfsroot >/proc/sys/kernel/nfs-root-name
echo 193.8.232.2:193.8.232.7::255.255.255.0:idefix \
>/proc/sys/kernel/nfs-root-addr
echo 255 >/proc/sys/kernel/real-root-dev
```

Note: The use of `/proc/sys/kernel/real-root-dev` to change the root filesystem is obsolete. See the Linux kernel source file `Documentation/admin-guide/initrd.rst` (or `Documentation/initrd.txt` before Linux 4.10) as well as `pivot_root(2)` and `pivot_root(8)` for information on the modern method of changing the root filesystem.

## Usage

The main motivation for implementing `initrd` was to allow for modular kernel configuration at system installation.

A possible system installation scenario is as follows:

1. The loader program boots from floppy or other media with a minimal kernel (e.g., support for `/dev/ram`, `/dev/initrd`, and the `ext2` filesystem) and loads `/dev/initrd` with a gzipped version of the initial filesystem.
2. The executable `/linuxrc` determines what is needed to (1) mount the normal root filesystem (i.e., device type, device drivers, filesystem) and (2) the distribution media (e.g., CD-ROM, network, tape, ...). This can be done by asking the user, by auto-probing, or by using a hybrid approach.
3. The executable `/linuxrc` loads the necessary modules from the initial root filesystem.
4. The executable `/linuxrc` creates and populates the root filesystem. (At this stage the normal root filesystem does not have to be a completed system yet.)
5. The executable `/linuxrc` sets `/proc/sys/kernel/real-root-dev`, `umount /proc`, the

normal root filesystem and any other filesystems it has mounted, and then terminates.

6. The kernel then mounts the normal root filesystem.

7. Now that the filesystem is accessible and intact, the boot loader can be installed.

8. The boot loader is configured to load into `/dev/initrd` a filesystem with the set of modules that was used to bring up the system. (e.g., Device `/dev/ram0` can be modified, then unmounted, and finally, the image is written from `/dev/ram0` to a file.)

9. The system is now bootable and additional installation tasks can be performed.

The key role of `/dev/initrd` in the above is to reuse the configuration data during normal system operation without requiring initial kernel selection, a large generic kernel or, recompiling the kernel.

A second scenario is for installations where Linux runs on systems with different hardware configurations in a single administrative network. In such cases, it may be desirable to use only a small set of kernels (ideally only one) and to keep the system-specific part of configuration information as small as possible. In this case, create a common file with all needed modules. Then, only the `/linuxrc` file or a file executed by `/linuxrc` would be different.

A third scenario is more convenient recovery disks. Because information like the location of the root filesystem partition is not needed at boot time, the system loaded from `/dev/initrd` can use a dialog and/or auto-detection followed by a possible sanity check.

Last but not least, Linux distributions on CD-ROM may use `initrd` for easy installation from the CD-ROM. The distribution can use `LOADLIN` to directly load `/dev/initrd` from CD-ROM without the need of any floppies. The distribution could also use a LILO boot floppy and then bootstrap a bigger RAM disk via `/dev/initrd` from the CD-ROM.

## FILES

`/dev/initrd`

`/dev/ram0`

`/linuxrc`

`/initrd`

## NOTES

1. With the current kernel, any filesystems that remain mounted when `/dev/ram0` is moved from `/` to `/initrd` continue to be accessible. However, the `/proc/mounts` entries are not updated.
2. With the current kernel, if directory `/initrd` does not exist, then `/dev/ram0` will not be fully unmounted if `/dev/ram0` is used by any process or has any filesystem mounted on it. If `/dev/ram0` is not fully unmounted, then `/dev/ram0` will remain in memory.
3. Users of `/dev/initrd` should not depend on the behavior given in the above notes. The behavior may change in future versions of the Linux kernel.

## SEE ALSO

`chown(1)`, `mknod(1)`, `ram(4)`, `freeramdisk(8)`, `rdev(8)`

`Documentation/admin-guide/initrd.rst` (or `Documentation/initrd.txt` before Linux 4.10) in the Linux kernel source tree, the LILO documentation, the LOADLIN documentation, the SYSLINUX documentation

## COLOPHON

This page is part of release 5.05 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

Linux

2019-03-06

INITRD(4)