



Windows PowerShell Get-Help on Cmdlet 'Set-JobTrigger'

PS:\>Get-HELP Set-JobTrigger -Full

NAME

Set-JobTrigger

SYNOPSIS

Changes the job trigger of a scheduled job.

SYNTAX

```
Set-JobTrigger [-InputObject] <Microsoft.PowerShell.ScheduledJob.ScheduledJobTrigger[]> [-At <System.DateTime>]
[-AtLogOn] [-AtStartup] [-Daily] [-DaysInterval
<System.Int32>] [-DaysOfWeek {Sunday | Monday | Tuesday | Wednesday | Thursday | Friday | Saturday}] [-Once]
[-PassThru] [-RandomDelay <System.TimeSpan>]
[-RepeatIndefinitely] [-RepetitionDuration <System.TimeSpan>] [-RepetitionInterval <System.TimeSpan>] [-User
<System.String>] [-Weekly] [-WeeksInterval
<System.Int32>] [<CommonParameters>]
```

DESCRIPTION

The 'Set-JobTrigger' cmdlet changes the properties of the job triggers of scheduled jobs. You can use it to change the time or frequency at which the jobs start or to

change from a time-based schedules to schedules that are triggered by a logon or startup.

A job trigger defines a recurring schedule or conditions for starting a scheduled job. Although job triggers are not saved to disk, you can change the job triggers of scheduled jobs, which are saved to disk.

To change a job trigger of a scheduled job, begin by using the ``Get-JobTrigger`` cmdlet to get the job trigger of a scheduled job. Then, pipe the trigger to ``Set-JobTrigger`` or save the trigger in a variable and use the `InputObject` parameter of ``Set-JobTrigger`` cmdlet to identify the trigger. Use the remaining parameters of ``Set-JobTrigger`` to change the job trigger.

When you change the type of a job trigger, such as changing a job trigger from a daily or weekly trigger to an `AtLogon` trigger, the original trigger properties are deleted. However, if you change the values of the trigger, but not its type, such as changing the days in a weekly trigger, only the properties that you specify are changed. All other properties of the original job trigger are retained.

``Set-JobTrigger`` is one of a collection of job scheduling cmdlets in the `PSScheduledJob` module that is included in Windows PowerShell.

For more information about Scheduled Jobs, see the About topics in the `PSScheduledJob` module. Import the `PSScheduledJob` module and then type: ``Get-Help about_Scheduled*`` or see `about_Scheduled_Jobs` (About/about_Scheduled_Jobs.md).

This cmdlet was introduced in Windows PowerShell 3.0.

PARAMETERS

`-At <System.DateTime>`

Starts the job at the specified date and time. Enter a `DateTime` object, such as one that the ``Get-Date`` cmdlet returns, or a string that can be converted to a time, such as ``April 19, 2012 15:00``, ``12/31/2013 9:00 PM``, or ``3am``.

If you don't specify an element of the DateTime object, such as seconds, that element of the job trigger is not changed.

If the original job trigger didn't

include a DateTime object and you omit an element, the job trigger is created with the corresponding element from the current date and time.

When using the Once parameter, set the value of the At parameter to a particular date and time. Because the default date in a DateTime object is the current date,

setting a time before the current time without an explicit date results in a job trigger for a time in the past. DateTime objects, and strings that are converted

to DateTime objects, are automatically adjusted to be compatible with the date and time formats selected for the local computer in Region and Language in Control

Panel.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-AtLogOn <System.Management.Automation.SwitchParameter>

Starts the scheduled job when the specified users log on to the computer. To specify a user, use the User parameter.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-AtStartup <System.Management.Automation.SwitchParameter>

Starts the scheduled job when Windows starts.

Required?	false
-----------	-------

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-Daily <System.Management.Automation.SwitchParameter>

Specifies a recurring daily job schedule. Use the other parameters in the Daily parameter set to specify the schedule details.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-DaysInterval <System.Int32>

Specifies the number of days between occurrences on a daily schedule. For example, a value of `3` starts the scheduled job on days `1`, `4`, `7` and so on. The default value is `1`.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-DaysOfWeek <System.DayOfWeek[]>

Specifies the days of the week on which a weekly scheduled job runs. Enter day names, such as `Monday`, `Thursday`, integers `0`-`6`, where `0` represents Sunday, or an asterisk (`*`) to represent every day. This parameter is required in the Weekly parameter set.

Day names are converted to their integer values in the job trigger. When you enclose day names in quotation marks in a command, enclose each day name in separate

quotation marks, such as `"Monday", "Tuesday"`. If you enclose multiple day names in a single quotation mark pair, the corresponding integer values are summed.

For example, `"Monday, Tuesday" (1 + 2)` results in a value of `Wednesday` (3).

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-InputObject <Microsoft.PowerShell.ScheduledJob.ScheduledJobTrigger[]>

Specifies the job triggers. Enter a variable that contains ScheduledJobTrigger objects or type a command or expression that gets ScheduledJobTrigger objects, such

as a `Get-JobTrigger` command. You can also pipe a ScheduledJobTrigger object to `Set-JobTrigger`.

If you specify multiple job triggers, `Set-JobTrigger` makes the same changes to all job triggers.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Once <System.Management.Automation.SwitchParameter>

Specifies a non-recurring (one time) schedule.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Returns the job triggers that changed. By default, this cmdlet does not generate any output.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-RandomDelay <System.TimeSpan>

Enables a random delay that begins at the scheduled start time, and sets the maximum delay value. The length of the delay is set pseudo-randomly for each start

and varies from no delay to the time specified by the value of this parameter. The default value, zero (`00:00:00`), disables the random delay.

Enter a timespan object, such as one returned by the `New-TimeSpan` cmdlet, or enter a value in ``<hours>:<minutes>:<seconds>`` format, which is automatically converted to a timespan object.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-RepeatIndefinitely <System.Management.Automation.SwitchParameter>

This parameter, available starting in Windows PowerShell 4.0, eliminates the necessity of specifying a `TimeSpan.MaxValue` value for the `RepetitionDuration` parameter to run a scheduled job repeatedly, for an indefinite period.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False

Accept wildcard characters? false

-RepetitionDuration <System.TimeSpan>

Repeats the job until the specified time expires. The repetition frequency is determined by the value of the RepetitionInterval parameter. For example, if the

value of RepetitionInterval is 5 minutes and the value of RepetitionDuration is 2 hours, the job is triggered every five minutes for two hours.

Enter a timespan object, such as one that the `New-TimeSpan` cmdlet returns or a string that can be converted to a timespan object, such as `1:05:30`.

To run a job indefinitely, add the RepeatIndefinitely parameter instead.

To stop a job before the job trigger repetition duration expires, set the RepetitionDuration value to zero (`0`).

To change the repetition duration or repetition interval of a Once job trigger, the command must include both the RepetitionInterval and RepetitionDuration

parameters. To change the repetition duration or repetition intervals of other types of job triggers, the command must include the Once , At , RepetitionInterval

and RepetitionDuration parameters.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-RepetitionInterval <System.TimeSpan>

Repeats the job at the specified time interval. For example, if the value of this parameter is 2 hours, the job is triggered every two hours. The default value,

`0`, does not repeat the job.

Enter a timespan object, such as one that the `New-TimeSpan` cmdlet returns or a string that can be converted to a

timespan object, such as `1:05:30`.

To change the repetition duration or repetition interval of a Once job trigger, the command must include both the RepetitionInterval and RepetitionDuration

parameters. To change the repetition duration or repetition intervals of other types of job triggers, the command must include the Once , At , RepetitionInterval and RepetitionDuration parameters.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-User <System.String>

Specifies the users who trigger an AtLogon start of a scheduled job. Enter the name of a user in ``<UserName>`` or ``<Domain><Username>`` format or enter an asterisk (*) to represent all users. The default value is all users.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Weekly <System.Management.Automation.SwitchParameter>

Specifies a recurring weekly job schedule. Use the other parameters in the Weekly parameter set to specify the schedule details.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False

Accept wildcard characters? false

-WeeksInterval <System.Int32>

Specifies the number of weeks between occurrences on a weekly job schedule. For example, a value of `3` starts the scheduled job on weeks `1`, `4`, `7` and so on.

The default value is `1`.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.PowerShell.ScheduledJob.ScheduledJobTrigger

You can pipe a job trigger to this cmdlet.

OUTPUTS

None

By default, this cmdlet returns no output.

Microsoft.PowerShell.ScheduledJob.ScheduledJobTrigger

When you use the PassThru parameter, this cmdlet returns the job triggers that it changed.

- Job triggers have a JobDefinition property that associates them with the scheduled job. When you change the job trigger of a scheduled job, the job is

changed. You do not need to use a ``Set-ScheduledJob`` command to apply the changed trigger to the scheduled job.

----- Example 1: Change the days in a job trigger -----

```
Get-JobTrigger -Name "DeployPackage"
```

Id	Frequency	Time	DaysOfWeek	Enabled
--	-----	----	-----	-----
1	Weekly	9/29/2011 12:00:00 AM	{Wednesday, Saturday}	True

```
Get-JobTrigger -Name "DeployPackage" | Set-JobTrigger -DaysOfWeek "Wednesday", "Sunday" -Passthru
```

Id	Frequency	Time	DaysOfWeek	Enabled
--	-----	----	-----	-----
1	Weekly	9/29/2011 12:00:00 AM	{Wednesday, Sunday}	True

The first command uses the ``Get-JobTrigger`` cmdlet to get the job trigger of the ``DeployPackage`` scheduled job. The output shows that the trigger starts the job at midnight on Wednesdays and Saturdays.

The second command uses the ``Get-JobTrigger`` cmdlet to get the job trigger of the ``DeployPackage`` scheduled job. A pipeline operator (``|``) sends the trigger to the

``Set-JobTrigger`` cmdlet, which changes the job trigger so that it starts the ``DeployPackage`` job on Wednesdays and Sundays. The command uses the `Passthru` parameter to return the trigger after the change.

This command is not required; it is included only to show the effect of the trigger change.

----- Example 2: Change the job trigger type -----

```
Get-JobTrigger -Name "Inventory"
```

Id	Frequency	Time	DaysOfWeek	Enabled
--	-----	----	-----	-----
1	Daily	9/27/2011 11:00:00 PM		True
2	AtStartup		True	

```
Get-JobTrigger -Name "Inventory" -TriggerID 2 | Set-JobTrigger -Weekly -WeeksInterval 4 -DaysOfWeek Monday -At "12:00 AM"
```

Id	Frequency	Time	DaysOfWeek	Enabled
--	-----	----	-----	-----
1	Daily	9/27/2011 11:00:00 PM		True
2	Weekly	10/31/2011 12:00:00 AM {Monday}		True

The first command uses the ``Get-JobTrigger`` cmdlet to get the job trigger of the ``Inventory`` scheduled job. The output shows that the job has two triggers a daily trigger and an AtStartup trigger.

The second command uses the ``Get-JobTrigger`` cmdlet to get the AtStartup job trigger of the ``Inventory`` job. The command uses the `TriggerID` parameter to identify the

job trigger. A pipeline operator (``|``) sends the job trigger to the ``Set-JobTrigger`` cmdlet, which changes it to a weekly job trigger that runs every four weeks on

Monday at midnight. The command uses the `Passthru` parameter to return the trigger after the change.

This command is not required; it is included only to show the effect of the trigger change.

----- Example 3: Change the user on a remote job trigger -----

```
Invoke-Command -ComputerName "Server01" -ScriptBlock {Get-ScheduledJob | Get-JobTrigger | Where-Object {$_ .User} | Set-JobTrigger -User "Domain01/Admin02"}
```

This command changes the user in all AtLogon job triggers of scheduled jobs on the Server01 computer.

The command uses the `Invoke-Command` cmdlet to run a command on the Server01 computer.

The remote command begins with a `Get-ScheduledJob` command that gets all scheduled jobs on the computer. The scheduled jobs are piped to the `Get-JobTrigger` cmdlet,

which gets the job triggers of the scheduled jobs. Each job trigger contains a JobDefinition property that contains the scheduled job, so the trigger remains

associated with the scheduled job even when it is changed.

The job triggers are piped to the `Where-Object` cmdlet, which gets job triggers that have the User property. The selected job triggers are piped to the

`Set-JobTrigger` cmdlet, which changes the user to `Domain01\Admin02`.

----- Example 4: Change one of many job triggers -----

```
Get-JobTrigger -Name "SecurityCheck"
```

Id	Frequency	Time	DaysOfWeek	Enabled
1	Daily	4/24/2013 3:00:00 AM		True
2	Weekly	4/24/2013 4:00:00 PM	{Sunday}	True
3	Once	4/24/2013 4:00:00 PM		True

```
Get-JobTrigger -Name "SecurityCheck" -TriggerID 3 | Format-List -Property *
```

At : 4/24/2012 4:00:00 PM

DaysOfWeek :

Interval : 1

Frequency : Once

RandomDelay : 00:00:00

RepetitionInterval : 01:00:00

RepetitionDuration : 1.00:00:00

User :

Id : 3

Enabled : True

JobDefinition : Microsoft.PowerShell.ScheduledJob.ScheduledJobDefinition

```
Get-JobTrigger -Name "SecurityCheck" -TriggerId 3 | Set-JobTrigger -RepetitionInterval (New-TimeSpan -Minutes 90)
```

```
Get-JobTrigger -Name "SecurityCheck" -TriggerID 3 | Format-List -Property *
```

At : 4/24/2012 4:00:00 PM

DaysOfWeek :

Interval : 1

Frequency : Once

RandomDelay : 00:00:00

RepetitionInterval : 01:30:00

RepetitionDuration : 1.00:00:00

User :

Id : 3

Enabled : True

JobDefinition : Microsoft.PowerShell.ScheduledJob.ScheduledJobDefinition

The commands in this example changes the repetition interval of the Once job trigger of `SecurityCheck` scheduled job from every 60 minutes to every 90 minutes. The

`SecurityCheck` scheduled job has three job triggers, so the commands use the TriggerId parameter of the `Get-JobTrigger` cmdlet to identify the job trigger that is being changed.

The first command uses the `Get-JobTrigger` cmdlet to get all job triggers of the `SecurityCheck` scheduled job. The output, which displays the IDs of the job

triggers, reveals that the Once job trigger has an ID of `3`.

The second command uses the TriggerID parameter of the `Get-JobTrigger` cmdlet to get the Once trigger of the `SecurityCheck` scheduled job. The command pipes the

trigger to the `Format-List` cmdlet, which displays all of the properties of the Once job trigger. The output shows that the trigger starts the job once every hour (

RepetitionInterval is 1 hour) for one day (RepetitionDuration is 1 day).

The third command changes the repetition interval of the job trigger from one hour to 90 minutes. The command does not return any output.

The fourth command displays the effect of the change. The output shows that the trigger starts the job once every 90 minutes (RepetitionInterval is 1 hour, 30 minutes) for one day (RepetitionDuration is 1 day).

RELATED LINKS

Online

Version:

https://learn.microsoft.com/powershell/module/psscheduledjob/set-jobtrigger?view=powershell-5.1&WT.mc_id=ps-gethelp

Add-JobTrigger

Disable-JobTrigger

Disable-ScheduledJob

Enable-JobTrigger

Enable-ScheduledJob

Get-JobTrigger

Get-ScheduledJob

Get-ScheduledJobOption

New-JobTrigger

New-ScheduledJobOption

Register-ScheduledJob

Remove-JobTrigger

Set-JobTrigger

Set-ScheduledJob

Set-ScheduledJobOption

Unregister-ScheduledJob