



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'SSL_get_srp_username.3ossl' command

`$ man SSL_get_srp_username.3ossl`

SSL_CTX_SET_SRP_PASSWORD(3ossl) OpenSSL SSL_CTX_SET_SRP_PASSWORD(3ossl)

NAME

SSL_CTX_set_srp_username, SSL_CTX_set_srp_password,
SSL_CTX_set_srp_strength, SSL_CTX_set_srp_cb_arg,
SSL_CTX_set_srp_username_callback, SSL_CTX_set_srp_client_pwd_callback,
SSL_CTX_set_srp_verify_param_callback, SSL_set_srp_server_param,
SSL_set_srp_server_param_pw, SSL_get_srp_g, SSL_get_srp_N,
SSL_get_srp_username, SSL_get_srp_userinfo - SRP control operations

SYNOPSIS

```
#include <openssl/ssl.h>
```

The following functions have been deprecated since OpenSSL 3.0, and can be hidden entirely by defining OPENSSL_API_COMPAT with a suitable version value, see openssl_user_macros(7):

```
int SSL_CTX_set_srp_username(SSL_CTX *ctx, char *name);  
int SSL_CTX_set_srp_password(SSL_CTX *ctx, char *password);  
int SSL_CTX_set_srp_strength(SSL_CTX *ctx, int strength);  
int SSL_CTX_set_srp_cb_arg(SSL_CTX *ctx, void *arg);  
int SSL_CTX_set_srp_username_callback(SSL_CTX *ctx,  
int (*cb) (SSL *s, int *ad, void *arg));
```

```

int SSL_CTX_set_srp_client_pwd_callback(SSL_CTX *ctx,
                                         char *(*cb) (SSL *s, void *arg));

int SSL_CTX_set_srp_verify_param_callback(SSL_CTX *ctx,
                                           int (*cb) (SSL *s, void *arg));

int SSL_set_srp_server_param(SSL *s, const BIGNUM *N, const BIGNUM *g,
                             BIGNUM *sa, BIGNUM *v, char *info);

int SSL_set_srp_server_param_pw(SSL *s, const char *user, const char *pass,
                                const char *grp);

BIGNUM *SSL_get_srp_g(SSL *s);
BIGNUM *SSL_get_srp_N(SSL *s);

char *SSL_get_srp_username(SSL *s);
char *SSL_get_srp_userinfo(SSL *s);

```

DESCRIPTION

All of the functions described on this page are deprecated. There are no available replacement functions at this time.

These functions provide access to SRP (Secure Remote Password) parameters, an alternate authentication mechanism for TLS. SRP allows the use of usernames and passwords over unencrypted channels without revealing the password to an eavesdropper. SRP also supplies a shared secret at the end of the authentication sequence that can be used to generate encryption keys.

The SRP protocol, version 3 is specified in RFC 2945. SRP version 6 is described in RFC 5054 with applications to TLS authentication.

The `SSL_CTX_set_srp_username()` function sets the SRP username for `ctx`.

This should be called on the client prior to creating a connection to the server. The length of name must be shorter or equal to 255

characters.

The `SSL_CTX_set_srp_password()` function sets the SRP password for `ctx`.

This may be called on the client prior to creating a connection to the

server. This overrides the effect of

`SSL_CTX_set_srp_client_pwd_callback()`.

The `SSL_CTX_set_srp_strength()` function sets the SRP strength for `ctx`.

This is the minimal length of the SRP prime in bits. If not specified

1024 is used. If not satisfied by the server key exchange the

connection will be rejected.

The `SSL_CTX_set_srp_cb_arg()` function sets an extra parameter that will

be passed to all following callbacks as `arg`.

The `SSL_CTX_set_srp_username_callback()` function sets the server side

callback that is invoked when an SRP username is found in a

`ClientHello`. The callback parameters are the SSL connection `s`, a

writable error flag `ad` and the extra argument `arg` set by

`SSL_CTX_set_srp_cb_arg()`. This callback should setup the server for

the key exchange by calling `SSL_set_srp_server_param()` with the

appropriate parameters for the received username. The username can be

obtained by calling `SSL_get_srp_username()`. See `SRP_VBASE_init(3)` to

parse the verifier file created by `openssl-srp(1)` or

`SRP_create_verifier(3)` to generate it. The callback should return

`SSL_ERROR_NONE` to proceed with the server key exchange, `SSL3_AL_FATAL`

for a fatal error or any value < 0 for a retryable error. In the event

of a `SSL3_AL_FATAL` the alert flag given by `*al` will be sent back. By

default this will be `SSL_AD_UNKNOWN_PSK_IDENTITY`.

The `SSL_CTX_set_srp_client_pwd_callback()` function sets the client

password callback on the client. The callback parameters are the SSL

connection `s` and the extra argument `arg` set by

SSL_CTX_set_srp_cb_arg(). The callback will be called as part of the generation of the client secrets. It should return the client password in text form or NULL to abort the connection. The resulting memory will be freed by the library as part of the callback resolution. This overrides the effect of SSL_CTX_set_srp_password().

The SSL_CTX_set_srp_verify_param_callback() sets the SRP gN parameter verification callback on the client. This allows the client to perform custom verification when receiving the server SRP proposed parameters.

The callback parameters are the SSL connection s and the extra argument arg set by SSL_CTX_set_srp_cb_arg(). The callback should return a positive value to accept the server parameters. Returning 0 or a negative value will abort the connection. The server parameters can be obtained by calling SSL_get_srp_N() and SSL_get_srp_g(). Sanity checks are already performed by the library after the handshake (B % N non zero, check against the strength parameter) and are not necessary. If no callback is set the g and N parameters will be checked against known RFC 5054 values.

The SSL_set_srp_server_param() function sets all SRP parameters for the connection s. N and g are the SRP group parameters, sa is the user salt, v the password verifier and info is the optional user info.

The SSL_set_srp_server_param_pw() function sets all SRP parameters for the connection s by generating a random salt and a password verifier. user is the username, pass the password and grp the SRP group parameters identifier for SRP_get_default_gN(3).

The SSL_get_srp_g() function returns the SRP group generator for s, or from the underlying SSL_CTX if it is NULL.

The SSL_get_srp_N() function returns the SRP prime for s, or from the underlying SSL_CTX if it is NULL.

The `SSL_get_srp_username()` function returns the SRP username for `s`, or from the underlying `SSL_CTX` if it is `NULL`.

The `SSL_get_srp_userinfo()` function returns the SRP user info for `s`, or from the underlying `SSL_CTX` if it is `NULL`.

RETURN VALUES

All `SSL_CTX_set_*` functions return 1 on success and 0 on failure.

`SSL_set_srp_server_param()` returns 1 on success and -1 on failure.

The `SSL_get_SRP_*` functions return a pointer to the requested data, the memory is owned by the library and should not be freed by the caller.

EXAMPLES

Setup SRP parameters on the client:

```
#include <openssl/ssl.h>

const char *username = "username";
const char *password = "password";

SSL_CTX *ctx = SSL_CTX_new(TLS_client_method());
if (!ctx)
    /* Error */
if (!SSL_CTX_set_srp_username(ctx, username))
    /* Error */
if (!SSL_CTX_set_srp_password(ctx, password))
    /* Error */
```

Setup SRP server with verifier file:

```

#include <openssl/srp.h>
#include <openssl/ssl.h>

const char *srpvfile = "password.srpv";

int srpServerCallback(SSL *s, int *ad, void *arg)
{
    SRP_VBASE *srpData = (SRP_VBASE*) arg;
    char *username = SSL_get_srp_username(s);

    SRP_user_pwd *user_pwd = SRP_VBASE_get1_by_user(srpData, username);
    if (!user_pwd)
        /* Error */
        return SSL3_AL_FATAL;

    if (SSL_set_srp_server_param(s, user_pwd->N, user_pwd->g,
        user_pwd->s, user_pwd->v, user_pwd->info) < 0)
        /* Error */

    SRP_user_pwd_free(user_pwd);
    return SSL_ERROR_NONE;
}

SSL_CTX *ctx = SSL_CTX_new(TLS_server_method());
if (!ctx)
    /* Error */

/*
 * seedKey should contain a NUL terminated sequence
 * of random non NUL bytes
 */
const char *seedKey;

```

```
SRP_VBASE *srpData = SRP_VBASE_new(seedKey);  
if (SRP_VBASE_init(srpData, (char*) srpvfile) != SRP_NO_ERROR)  
    /* Error */
```

```
SSL_CTX_set_srp_cb_arg(ctx, srpData);  
SSL_CTX_set_srp_username_callback(ctx, srpServerCallback);
```

SEE ALSO

ssl(7), openssl-srp(1), SRP_VBASE_new(3), SRP_create_verifier(3)

HISTORY

These functions were added in OpenSSL 1.0.1 and deprecated in OpenSSL 3.0.

COPYRIGHT

Copyright 2018-2021 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.

3.0.7 2023-07-13 SSL_CTX_SET_SRP_PASSWORD(3openssl)