



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'SSL_CTX_use_serverinfo_ex.3ossl'

\$ man SSL_CTX_use_serverinfo_ex.3ossl

SSL_CTX_USE_SERVERINFO(3ossl) OpenSSL SSL_CTX_USE_SERVERINFO(3ossl)

NAME

SSL_CTX_use_serverinfo_ex, SSL_CTX_use_serverinfo,
SSL_CTX_use_serverinfo_file - use serverinfo extension

SYNOPSIS

```
#include <openssl/ssl.h>
```

```
int SSL_CTX_use_serverinfo_ex(SSL_CTX *ctx, unsigned int version,  
                             const unsigned char *serverinfo,  
                             size_t serverinfo_length);
```

```
int SSL_CTX_use_serverinfo(SSL_CTX *ctx, const unsigned char *serverinfo,  
                           size_t serverinfo_length);
```

```
int SSL_CTX_use_serverinfo_file(SSL_CTX *ctx, const char *file);
```

DESCRIPTION

These functions load "serverinfo" TLS extensions into the SSL_CTX. A "serverinfo" extension is returned in response to an empty ClientHello Extension.

SSL_CTX_use_serverinfo_ex() loads one or more serverinfo extensions from a byte array into ctx. The version parameter specifies the format of the byte array provided in *serverinfo which is of length serverinfo_length.

If version is SSL_SERVERINFOV2 then the extensions in the array must consist of a 4-byte context, a 2-byte Extension Type, a 2-byte length, and then length bytes of extension_data. The context and type values have the same meaning as for SSL_CTX_add_custom_ext(3). If serverinfo is being loaded for extensions to be added to a Certificate message, then the extension will only be added for the first certificate in the message (which is always the end-entity certificate).

If version is SSL_SERVERINFOV1 then the extensions in the array must consist of a 2-byte Extension Type, a 2-byte length, and then length bytes of extension_data. The type value has the same meaning as for SSL_CTX_add_custom_ext(3). The following default context value will be used in this case:

```
SSL_EXT_TLS1_2_AND_BELOW_ONLY | SSL_EXT_CLIENT_HELLO  
| SSL_EXT_TLS1_2_SERVER_HELLO | SSL_EXT_IGNORE_ON_RESUMPTION
```

SSL_CTX_use_serverinfo() does the same thing as SSL_CTX_use_serverinfo_ex() except that there is no version parameter so a default version of SSL_SERVERINFOV1 is used instead.

SSL_CTX_use_serverinfo_file() loads one or more serverinfo extensions from file into ctx. The extensions must be in PEM format. Each

extension must be in a format as described above for
SSL_CTX_use_serverinfo_ex(). Each PEM extension name must begin with
the phrase "BEGIN SERVERINFOV2 FOR " for SSL_SERVERINFOV2 data or
"BEGIN SERVERINFO FOR " for SSL_SERVERINFOV1 data.

If more than one certificate (RSA/DSA) is installed using
SSL_CTX_use_certificate(), the serverinfo extension will be loaded into
the last certificate installed. If e.g. the last item was a RSA
certificate, the loaded serverinfo extension data will be loaded for
that certificate. To use the serverinfo extension for multiple
certificates, SSL_CTX_use_serverinfo() needs to be called multiple
times, once after each time a certificate is loaded via a call to
SSL_CTX_use_certificate().

RETURN VALUES

On success, the functions return 1. On failure, the functions return
0. Check out the error stack to find out the reason.

SEE ALSO

ssl(7)

COPYRIGHT

Copyright 2013-2017 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use
this file except in compliance with the License. You can obtain a copy
in the file LICENSE in the source distribution or at
<<https://www.openssl.org/source/license.html>>.