



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'login.defs.5'***

**\$ man login.defs.5**

LOGIN.DEFS(5) File Formats and Conversions LOGIN.DEFS(5)

#### **NAME**

login.defs - shadow password suite configuration

#### **DESCRIPTION**

The /etc/login.defs file defines the site-specific configuration for the shadow password suite. This file is required. Absence of this file will not prevent system operation, but will probably result in undesirable operation.

This file is a readable text file, each line of the file describing one configuration parameter. The lines consist of a configuration name and value, separated by whitespace. Blank lines and comment lines are ignored. Comments are introduced with a "#" pound sign and the pound sign must be the first non-white character of the line.

Parameter values may be of four types: strings, booleans, numbers, and long numbers. A string is comprised of any printable characters. A boolean should be either the value yes or no. An undefined boolean parameter or one with a value other than these will be given a no value. Numbers (both regular and long) may be either decimal values,

octal values (precede the value with 0) or hexadecimal values (precede the value with 0x). The maximum value of the regular and long numeric parameters is machine-dependent.

Please note that the parameters in this configuration file control the behavior of the tools from the shadow-utils component. None of these tools uses the PAM mechanism, and the utilities that use PAM (such as the passwd command) should be configured elsewhere. The only values that affect PAM modules are ENCRYPT\_METHOD and SHA\_CRYPT\_MAX\_ROUNDS for pam\_unix module, FAIL\_DELAY for pam\_failedelay module, and UMASK for pam\_umask module. Refer to pam(8) for more information.

The following configuration items are provided:

#### **CHFN\_AUTH (boolean)**

If yes, the chfn program will require authentication before making any changes, unless run by the superuser.

#### **CHFN\_RESTRICT (string)**

This parameter specifies which values in the gecos field of the /etc/passwd file may be changed by regular users using the chfn program. It can be any combination of letters f, r, w, h, for Full name, Room number, Work phone, and Home phone, respectively. For backward compatibility, yes is equivalent to rwh and no is equivalent to frwh. If not specified, only the superuser can make any changes. The most restrictive setting is better achieved by not installing chfn SUID.

#### **CHSH\_AUTH (boolean)**

If yes, the chsh program will require authentication before making any changes, unless run by the superuser.

#### **CONSOLE (string)**

If defined, either full pathname of a file containing device names (one per line) or a ":" delimited list of device names. Root logins will be allowed only upon these devices.

If not defined, root will be allowed on any device.

The device should be specified without the /dev/ prefix.

#### **CONSOLE\_GROUPS (string)**

List of groups to add to the user's supplementary groups set when logging in on the console (as determined by the CONSOLE setting).

Default is none.

Use with caution - it is possible for users to gain permanent access to these groups, even when not logged in on the console.

#### CREATE\_HOME (boolean)

Indicate if a home directory should be created by default for new users.

This setting does not apply to system users, and can be overridden on the command line.

#### DEFAULT\_HOME (boolean)

Indicate if login is allowed if we can't cd to the home directory.

Default is no.

If set to yes, the user will login in the root (/) directory if it is not possible to cd to her home directory.

#### ENCRYPT\_METHOD (string)

This defines the system default encryption algorithm for encrypting passwords (if no algorithm are specified on the command line).

It can take one of these values: DES (default), MD5, SHA256, SHA512. MD5 and DES should not be used for new hashes, see crypt(5) for recommendations.

Note: this parameter overrides the MD5\_CRYPT\_ENAB variable.

#### ENV\_HZ (string)

If set, it will be used to define the HZ environment variable when a user login. The value must be preceded by HZ=. A common value on Linux is HZ=100.

#### ENV\_PATH (string)

If set, it will be used to define the PATH environment variable when a regular user login. The value is a colon separated list of paths (for example /bin:/usr/bin) and can be preceded by PATH=. The default value is PATH=/bin:/usr/bin.

#### ENV\_SUPATH (string)

If set, it will be used to define the PATH environment variable

when the superuser login. The value is a colon separated list of paths (for example /sbin:/bin:/usr/sbin:/usr/bin) and can be preceded by PATH=. The default value is PATH=/sbin:/bin:/usr/sbin:/usr/bin.

#### ENV\_TZ (string)

If set, it will be used to define the TZ environment variable when a user login. The value can be the name of a timezone preceded by TZ= (for example TZ=CST6CDT), or the full path to the file containing the timezone specification (for example /etc/tzname). If a full path is specified but the file does not exist or cannot be read, the default is to use TZ=CST6CDT.

#### ENVIRON\_FILE (string)

If this file exists and is readable, login environment will be read from it. Every line should be in the form name=value. Lines starting with a # are treated as comment lines and ignored.

#### ERASECHAR (number)

Terminal ERASE character (010 = backspace, 0177 = DEL). The value can be prefixed "0" for an octal value, or "0x" for an hexadecimal value.

#### FAIL\_DELAY (number)

Delay in seconds before being allowed another attempt after a login failure.

#### FAILLOG\_ENAB (boolean)

Enable logging and display of /var/log/faillog login failure info.

#### FAKE\_SHELL (string)

If set, login will execute this shell instead of the users' shell specified in /etc/passwd.

#### FTMP\_FILE (string)

If defined, login failures will be logged in this file in a utmp format.

#### GID\_MAX (number), GID\_MIN (number)

Range of group IDs used for the creation of regular groups by useradd, groupadd, or newusers.

The default value for GID\_MIN (resp. GID\_MAX) is 1000 (resp. 60000).

#### **HMAC\_CRYPTO\_ALGO (string)**

Used to select the HMAC cryptography algorithm that the pam\_timestamp module is going to use to calculate the keyed-hash message authentication code.

Note: Check hmac(3) to see the possible algorithms that are available in your system.

#### **HOME\_MODE (number)**

The mode for new home directories. If not specified, the UMASK is used to create the mode.

useradd and newusers use this to set the mode of the home directory they create.

#### **HUSHLOGIN\_FILE (string)**

If defined, this file can inhibit all the usual chatter during the login sequence. If a full pathname is specified, then hushed mode will be enabled if the user's name or shell are found in the file.

If not a full pathname, then hushed mode will be enabled if the file exists in the user's home directory.

#### **ISSUE\_FILE (string)**

If defined, this file will be displayed before each login prompt.

#### **KILLCHAR (number)**

Terminal KILL character (025 = CTRL/U).

The value can be prefixed "0" for an octal value, or "0x" for an hexadecimal value.

#### **LASTLOG\_ENAB (boolean)**

Enable logging and display of /var/log/lastlog login time info.

#### **LASTLOG\_UID\_MAX (number)**

Highest user ID number for which the lastlog entries should be updated. As higher user IDs are usually tracked by remote user identity and authentication services there is no need to create a huge sparse lastlog file for them.

No LASTLOG\_UID\_MAX option present in the configuration means that

there is no user ID limit for writing lastlog entries.

#### LOG\_OK\_LOGINS (boolean)

Enable logging of successful logins.

#### LOG\_UNKFAIL\_ENAB (boolean)

Enable display of unknown usernames when login failures are recorded.

Note: logging unknown usernames may be a security issue if an user enter her password instead of her login name.

#### LOGIN\_ATTEMPTS (number)

Maximum number of login retries in case of bad password.

#### LOGIN\_STRING (string)

The string used for prompting a password. The default is to use "Password: ", or a translation of that string. If you set this variable, the prompt will not be translated.

If the string contains %s, this will be replaced by the user's name.

#### LOGIN\_TIMEOUT (number)

Max time in seconds for login.

#### MAIL\_CHECK\_ENAB (boolean)

Enable checking and display of mailbox status upon login.

You should disable it if the shell startup files already check for mail ("mailx -e" or equivalent).

#### MAIL\_DIR (string)

The mail spool directory. This is needed to manipulate the mailbox when its corresponding user account is modified or deleted. If not specified, a compile-time default is used.

#### MAIL\_FILE (string)

Defines the location of the users mail spool files relatively to their home directory.

The MAIL\_DIR and MAIL\_FILE variables are used by useradd, usermod, and userdel to create, move, or delete the user's mail spool.

If MAIL\_CHECK\_ENAB is set to yes, they are also used to define the MAIL environment variable.

## MAX\_MEMBERS\_PER\_GROUP (number)

Maximum members per group entry. When the maximum is reached, a new group entry (line) is started in /etc/group (with the same name, same password, and same GID).

The default value is 0, meaning that there are no limits in the number of members in a group.

This feature (split group) permits to limit the length of lines in the group file. This is useful to make sure that lines for NIS groups are not larger than 1024 characters.

If you need to enforce such limit, you can use 25.

Note: split groups may not be supported by all tools (even in the Shadow toolsuite). You should not use this variable unless you really need it.

## MD5\_CRYPT\_ENAB (boolean)

Indicate if passwords must be encrypted using the MD5-based algorithm. If set to yes, new passwords will be encrypted using the MD5-based algorithm compatible with the one used by recent releases of FreeBSD. It supports passwords of unlimited length and longer salt strings. Set to no if you need to copy encrypted passwords to other systems which don't understand the new algorithm. Default is no.

This variable is superseded by the ENCRYPT\_METHOD variable or by any command line option used to configure the encryption algorithm.

This variable is deprecated. You should use ENCRYPT\_METHOD.

## MOTD\_FILE (string)

If defined, ":" delimited list of "message of the day" files to be displayed upon login.

## NOLOGINS\_FILE (string)

If defined, name of file whose presence will inhibit non-root logins. The contents of this file should be a message indicating why logins are inhibited.

## NONEXISTENT (string)

If a system account intentionally does not have a home directory

that exists, this string can be provided in the /etc/passwd entry for the account to indicate this. The result is that pwck will not emit a spurious warning for this account.

#### OBSCURE\_CHECKS\_ENAB (boolean)

Enable additional checks upon password changes.

#### PASS\_ALWAYS\_WARN (boolean)

Warn about weak passwords (but still allow them) if you are root.

#### PASS\_CHANGE\_TRIES (number)

Maximum number of attempts to change password if rejected (too easy).

#### PASS\_MAX\_DAYS (number)

The maximum number of days a password may be used. If the password is older than this, a password change will be forced. If not specified, -1 will be assumed (which disables the restriction).

#### PASS\_MIN\_DAYS (number)

The minimum number of days allowed between password changes. Any password changes attempted sooner than this will be rejected. If not specified, 0 will be assumed (which disables the restriction).

#### PASS\_WARN\_AGE (number)

The number of days warning given before a password expires. A zero means warning is given only upon the day of expiration, a negative value means no warning is given. If not specified, no warning will be provided.

PASS\_MAX\_DAYS, PASS\_MIN\_DAYS and PASS\_WARN\_AGE are only used at the time of account creation. Any changes to these settings won't affect existing accounts.

#### PASS\_MAX\_LEN (number), PASS\_MIN\_LEN (number)

Number of significant characters in the password for crypt().

PASS\_MAX\_LEN is 8 by default. Don't change unless your crypt() is better. This is ignored if MD5\_CRYPT\_ENAB set to yes.

#### PORTTIME\_CHECKS\_ENAB (boolean)

Enable checking of time restrictions specified in /etc/porttime.

#### QUOTAS\_ENAB (boolean)

Enable setting of resource limits from /etc/limits and ulimit, umask, and niceness from the user's passwd gecos field.

#### SHA\_CRYPT\_MIN\_ROUNDS (number), SHA\_CRYPT\_MAX\_ROUNDS (number)

When ENCRYPT\_METHOD is set to SHA256 or SHA512, this defines the number of SHA rounds used by the encryption algorithm by default (when the number of rounds is not specified on the command line).

With a lot of rounds, it is more difficult to brute forcing the password. But note also that more CPU resources will be needed to authenticate users.

If not specified, the libc will choose the default number of rounds (5000), which is orders of magnitude too low for modern hardware.

The values must be inside the 1000-999,999,999 range.

If only one of the SHA\_CRYPT\_MIN\_ROUNDS or SHA\_CRYPT\_MAX\_ROUNDS values is set, then this value will be used.

If SHA\_CRYPT\_MIN\_ROUNDS > SHA\_CRYPT\_MAX\_ROUNDS, the highest value will be used.

#### SULOG\_FILE (string)

If defined, all su activity is logged to this file.

#### SU\_NAME (string)

If defined, the command name to display when running "su -". For example, if this is defined as "su" then a "ps" will display the command is "-su". If not defined, then "ps" would display the name of the shell actually being run, e.g. something like "-sh".

#### SU\_WHEEL\_ONLY (boolean)

If yes, the user must be listed as a member of the first gid 0 group in /etc/group (called root on most Linux systems) to be able to su to uid 0 accounts. If the group doesn't exist or is empty, no one will be able to su to uid 0.

#### SUB\_GID\_MIN (number), SUB\_GID\_MAX (number), SUB\_GID\_COUNT (number)

If /etc/subuid exists, the commands useradd and newusers (unless the user already have subordinate group IDs) allocate SUB\_GID\_COUNT unused group IDs from the range SUB\_GID\_MIN to SUB\_GID\_MAX for each new user.

The default values for SUB\_GID\_MIN, SUB\_GID\_MAX, SUB\_GID\_COUNT are respectively 100000, 600100000 and 65536.

SUB\_UID\_MIN (number), SUB\_UID\_MAX (number), SUB\_UID\_COUNT (number)

If /etc/subuid exists, the commands useradd and newusers (unless the user already have subordinate user IDs) allocate SUB\_UID\_COUNT unused user IDs from the range SUB\_UID\_MIN to SUB\_UID\_MAX for each new user.

The default values for SUB\_UID\_MIN, SUB\_UID\_MAX, SUB\_UID\_COUNT are respectively 100000, 600100000 and 65536.

SYS\_GID\_MAX (number), SYS\_GID\_MIN (number)

Range of group IDs used for the creation of system groups by useradd, groupadd, or newusers.

The default value for SYS\_GID\_MIN (resp. SYS\_GID\_MAX) is 101 (resp. GID\_MIN-1).

SYS\_UID\_MAX (number), SYS\_UID\_MIN (number)

Range of user IDs used for the creation of system users by useradd or newusers.

The default value for SYS\_UID\_MIN (resp. SYS\_UID\_MAX) is 101 (resp. UID\_MIN-1).

SYSLOG\_SG\_ENAB (boolean)

Enable "syslog" logging of sg activity.

SYSLOG\_SU\_ENAB (boolean)

Enable "syslog" logging of su activity - in addition to sulog file logging.

TTYGROUP (string), TTYPERM (string)

The terminal permissions: the login tty will be owned by the TTYGROUP group, and the permissions will be set to TTYPERM.

By default, the ownership of the terminal is set to the user's primary group and the permissions are set to 0600.

TTYGROUP can be either the name of a group or a numeric group identifier.

If you have a write program which is "setgid" to a special group which owns the terminals, define TTYGROUP to the group number and

TTYPERM to 0620. Otherwise leave TTYGROUP commented out and assign

TTYPERM to either 622 or 600.

#### TTYTYPE\_FILE (string)

If defined, file which maps tty line to TERM environment parameter.

Each line of the file is in a format something like "vt100 tty01".

#### UID\_MAX (number), UID\_MIN (number)

Range of user IDs used for the creation of regular users by useradd

or newusers.

The default value for UID\_MIN (resp. UID\_MAX) is 1000 (resp.

60000).

#### ULIMIT (number)

Default ulimit value.

#### UMASK (number)

The file mode creation mask is initialized to this value. If not

specified, the mask will be initialized to 022.

useradd and newusers use this mask to set the mode of the home

directory they create if HOME\_MODE is not set.

It is also used by login to define users' initial umask. Note that

this mask can be overridden by the user's GECOS line (if

QUOTAS\_ENAB is set) or by the specification of a limit with the K

identifier in limits(5).

#### USERDEL\_CMD (string)

If defined, this command is run when removing a user. It should

remove any at/cron/print jobs etc. owned by the user to be removed

(passed as the first argument).

The return code of the script is not taken into account.

Here is an example script, which removes the user's cron, at and

print jobs:

```
#!/bin/sh

# Check for the required argument.

if [ $# != 1 ]; then

    echo "Usage: $0 username"

    exit 1
```

```
fi

# Remove cron jobs.

crontab -r -u $1

# Remove at jobs.

# Note that it will remove any jobs owned by the same UID,
# even if it was shared by a different username.

AT_SPOOL_DIR=/var/spool/cron/atjobs

find $AT_SPOOL_DIR -name "[^.]*" -type f -user $1 -delete \;

# Remove print jobs.

lprm $1

# All done.

exit 0
```

#### USERGROUPS\_ENAB (boolean)

Enable setting of the umask group bits to be the same as owner bits  
(examples: 022 -> 002, 077 -> 007) for non-root users, if the uid  
is the same as gid, and username is the same as the primary group  
name.

If set to yes, userdel will remove the user's group if it contains  
no more members, and useradd will create by default a group with  
the name of the user.

#### CROSS REFERENCES

The following cross references show which programs in the shadow  
password suite use which parameters.

##### chgpasswd

ENCRYPT\_METHOD MAX\_MEMBERS\_PER\_GROUP MD5\_CRYPT\_ENAB  
SHA\_CRYPT\_MAX\_ROUNDS SHA\_CRYPT\_MIN\_ROUNDS

##### chpasswd

ENCRYPT\_METHOD MD5\_CRYPT\_ENAB SHA\_CRYPT\_MAX\_ROUNDS  
SHA\_CRYPT\_MIN\_ROUNDS

##### gpasswd

ENCRYPT\_METHOD MAX\_MEMBERS\_PER\_GROUP MD5\_CRYPT\_ENAB  
SHA\_CRYPT\_MAX\_ROUNDS SHA\_CRYPT\_MIN\_ROUNDS

##### groupadd

GID\_MAX GID\_MIN MAX\_MEMBERS\_PER\_GROUP SYS\_GID\_MAX SYS\_GID\_MIN

groupdel  
MAX\_MEMBERS\_PER\_GROUP

groupmems  
MAX\_MEMBERS\_PER\_GROUP

groupmod  
MAX\_MEMBERS\_PER\_GROUP

grpck  
MAX\_MEMBERS\_PER\_GROUP

grpconv  
MAX\_MEMBERS\_PER\_GROUP

grpunconv  
MAX\_MEMBERS\_PER\_GROUP

lastlog  
LASTLOG\_UID\_MAX

newgrp / sg  
SYSLOG\_SG\_ENAB

newusers  
ENCRYPT\_METHOD GID\_MAX GID\_MIN MAX\_MEMBERS\_PER\_GROUP MD5\_CRYPT\_ENAB  
HOME\_MODE PASS\_MAX\_DAYS PASS\_MIN\_DAYS PASS\_WARN\_AGE  
SHA\_CRYPT\_MAX\_ROUNDS SHA\_CRYPT\_MIN\_ROUNDS SUB\_GID\_COUNT SUB\_GID\_MAX  
SUB\_GID\_MIN SUB\_UID\_COUNT SUB\_UID\_MAX SUB\_UID\_MIN SYS\_GID\_MAX  
SYS\_GID\_MIN SYS\_UID\_MAX SYS\_UID\_MIN UID\_MAX UID\_MIN UMASK

pwck  
PASS\_MAX\_DAYS PASS\_MIN\_DAYS PASS\_WARN\_AGE

pwconv  
PASS\_MAX\_DAYS PASS\_MIN\_DAYS PASS\_WARN\_AGE

useradd  
CREATE\_HOME GID\_MAX GID\_MIN HOME\_MODE LASTLOG\_UID\_MAX MAIL\_DIR  
MAX\_MEMBERS\_PER\_GROUP PASS\_MAX\_DAYS PASS\_MIN\_DAYS PASS\_WARN\_AGE  
SUB\_GID\_COUNT SUB\_GID\_MAX SUB\_GID\_MIN SUB\_UID\_COUNT SUB\_UID\_MAX  
SUB\_UID\_MIN SYS\_GID\_MAX SYS\_GID\_MIN SYS\_UID\_MAX SYS\_UID\_MIN UID\_MAX  
UID\_MIN UMASK

userdel

MAIL\_DIR MAIL\_FILE MAX\_MEMBERS\_PER\_GROUP USERDEL\_CMD

USERGROUPS\_ENAB

usermod

LASTLOG\_UID\_MAX MAIL\_DIR MAIL\_FILE MAX\_MEMBERS\_PER\_GROUP

SEE ALSO

login(1), passwd(1), su(1), passwd(5), shadow(5), pam(8).

shadow-utils 4.9

09/28/2022

LOGIN.DEFS(5)