



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'Locale::RecodeData::IBM281.3pm'

\$ man Locale::RecodeData::IBM281.3pm

Locale::RecodeData::IBM281(3pm)User Contributed Perl DocumentationLocale::RecodeData::IBM281(3pm)

NAME

Locale::RecodeData::IBM281 - Conversion routines for IBM281

SYNOPSIS

This module is internal to libintl. Do not use directly!

DESCRIPTION

This module is generated and contains the conversion tables and routines for IBM281.

COMMENTS

The following comments have been extracted from the original charmap:

version: 1.0

source: IBM 3174 Character Set Ref, GA27-3831-02, March 1990

alias EBCDIC-JP-E

alias CP281

Please note that aliases listed above are not necessarily valid!

CHARACTER TABLE

The following table is sorted in the same order as the original charmap. All character

codes are in hexadecimal. Please read 'ISO-10646' as 'ISO-10646-UCS4'.

Local | ISO-10646 | Description

-----+-----+-----		
Local	ISO-10646	Description
00	00000000	NULL (NUL)
01	00000001	START OF HEADING (SOH)
02	00000002	START OF TEXT (STX)
03	00000003	END OF TEXT (ETX)
04	0000009C	STRING TERMINATOR (ST)
05	00000009	CHARACTER TABULATION (HT)
06	00000086	START OF SELECTED AREA (SSA)
07	0000007F	DELETE (DEL)
08	00000097	END OF GUARDED AREA (EPA)
09	0000008D	REVERSE LINE FEED (RI)
0A	0000008E	SINGLE-SHIFT TWO (SS2)
0B	0000000B	LINE TABULATION (VT)
0C	0000000C	FORM FEED (FF)
0D	0000000D	CARRIAGE RETURN (CR)
0E	0000000E	SHIFT OUT (SO)
0F	0000000F	SHIFT IN (SI)
10	00000010	DATALINK ESCAPE (DLE)
11	00000011	DEVICE CONTROL ONE (DC1)
12	00000012	DEVICE CONTROL TWO (DC2)
13	00000013	DEVICE CONTROL THREE (DC3)
14	0000009D	OPERATING SYSTEM COMMAND (OSC)
15	00000085	NEXT LINE (NEL)
16	00000008	BACKSPACE (BS)
17	00000087	END OF SELECTED AREA (ESA)
18	00000018	CANCEL (CAN)
19	00000019	END OF MEDIUM (EM)
1A	00000092	PRIVATE USE TWO (PU2)
1B	0000008F	SINGLE-SHIFT THREE (SS3)
1C	0000001C	FILE SEPARATOR (IS4)

1D | 0000001D | GROUP SEPARATOR (IS3)
1E | 0000001E | RECORD SEPARATOR (IS2)
1F | 0000001F | UNIT SEPARATOR (IS1)
20 | 00000080 | PADDING CHARACTER (PAD)
21 | 00000081 | HIGH OCTET PRESET (HOP)
22 | 00000082 | BREAK PERMITTED HERE (BPH)
23 | 00000083 | NO BREAK HERE (NBH)
24 | 00000084 | INDEX (IND)
25 | 0000000A | LINE FEED (LF)
26 | 00000017 | END OF TRANSMISSION BLOCK (ETB)
27 | 0000001B | ESCAPE (ESC)
28 | 00000088 | CHARACTER TABULATION SET (HTS)
29 | 00000089 | CHARACTER TABULATION WITH JUSTIFICATION (HTJ)
2A | 0000008A | LINE TABULATION SET (VTS)
2B | 0000008B | PARTIAL LINE FORWARD (PLD)
2C | 0000008C | PARTIAL LINE BACKWARD (PLU)
2D | 00000005 | ENQUIRY (ENQ)
2E | 00000006 | ACKNOWLEDGE (ACK)
2F | 00000007 | BELL (BEL)
30 | 00000090 | DEVICE CONTROL STRING (DCS)
31 | 00000091 | PRIVATE USE ONE (PU1)
32 | 00000016 | SYNCHRONOUS IDLE (SYN)
33 | 00000093 | SET TRANSMIT STATE (STS)
34 | 00000094 | CANCEL CHARACTER (CCH)
35 | 00000095 | MESSAGE WAITING (MW)
36 | 00000096 | START OF GUARDED AREA (SPA)
37 | 00000004 | END OF TRANSMISSION (EOT)
38 | 00000098 | START OF STRING (SOS)
39 | 00000099 | SINGLE GRAPHIC CHARACTER INTRODUCER (SGCI)
3A | 0000009A | SINGLE CHARACTER INTRODUCER (SCI)
3B | 0000009B | CONTROL SEQUENCE INTRODUCER (CSI)
3C | 00000014 | DEVICE CONTROL FOUR (DC4)
3D | 00000015 | NEGATIVE ACKNOWLEDGE (NAK)

3E | 0000009E | PRIVACY MESSAGE (PM)
3F | 0000001A | SUBSTITUTE (SUB)
40 | 00000020 | SPACE
4A | 000000A3 | POUND SIGN
4B | 0000002E | FULL STOP
4C | 0000003C | LESS-THAN SIGN
4D | 00000028 | LEFT PARENTHESIS
4E | 0000002B | PLUS SIGN
4F | 0000007C | VERTICAL LINE
50 | 00000026 | AMPERSAND
5A | 00000021 | EXCLAMATION MARK
5B | 000000A5 | YEN SIGN
5C | 0000002A | ASTERISK
5D | 00000029 | RIGHT PARENTHESIS
5E | 0000003B | SEMICOLON
5F | 000000AC | NOT SIGN
60 | 0000002D | HYPHEN-MINUS
61 | 0000002F | SOLIDUS
6A | 000000A6 | BROKEN BAR
6B | 0000002C | COMMA
6C | 00000025 | PERCENT SIGN
6D | 0000005F | LOW LINE
6E | 0000003E | GREATER-THAN SIGN
6F | 0000003F | QUESTION MARK
79 | 00000060 | GRAVE ACCENT
7A | 0000003A | COLON
7B | 00000023 | NUMBER SIGN
7C | 00000040 | COMMERCIAL AT
7D | 00000027 | APOSTROPHE
7E | 0000003D | EQUALS SIGN
7F | 00000022 | QUOTATION MARK
81 | 00000061 | LATIN SMALL LETTER A
82 | 00000062 | LATIN SMALL LETTER B

83 | 00000063 | LATIN SMALL LETTER C
84 | 00000064 | LATIN SMALL LETTER D
85 | 00000065 | LATIN SMALL LETTER E
86 | 00000066 | LATIN SMALL LETTER F
87 | 00000067 | LATIN SMALL LETTER G
88 | 00000068 | LATIN SMALL LETTER H
89 | 00000069 | LATIN SMALL LETTER I
91 | 0000006A | LATIN SMALL LETTER J
92 | 0000006B | LATIN SMALL LETTER K
93 | 0000006C | LATIN SMALL LETTER L
94 | 0000006D | LATIN SMALL LETTER M
95 | 0000006E | LATIN SMALL LETTER N
96 | 0000006F | LATIN SMALL LETTER O
97 | 00000070 | LATIN SMALL LETTER P
98 | 00000071 | LATIN SMALL LETTER Q
99 | 00000072 | LATIN SMALL LETTER R
A1 | 0000203E | OVERLINE
A2 | 00000073 | LATIN SMALL LETTER S
A3 | 00000074 | LATIN SMALL LETTER T
A4 | 00000075 | LATIN SMALL LETTER U
A5 | 00000076 | LATIN SMALL LETTER V
A6 | 00000077 | LATIN SMALL LETTER W
A7 | 00000078 | LATIN SMALL LETTER X
A8 | 00000079 | LATIN SMALL LETTER Y
A9 | 0000007A | LATIN SMALL LETTER Z
C0 | 0000007B | LEFT CURLY BRACKET
C1 | 00000041 | LATIN CAPITAL LETTER A
C2 | 00000042 | LATIN CAPITAL LETTER B
C3 | 00000043 | LATIN CAPITAL LETTER C
C4 | 00000044 | LATIN CAPITAL LETTER D
C5 | 00000045 | LATIN CAPITAL LETTER E
C6 | 00000046 | LATIN CAPITAL LETTER F
C7 | 00000047 | LATIN CAPITAL LETTER G

C8 | 00000048 | LATIN CAPITAL LETTER H
C9 | 00000049 | LATIN CAPITAL LETTER I
D0 | 0000007D | RIGHT CURLY BRACKET
D1 | 0000004A | LATIN CAPITAL LETTER J
D2 | 0000004B | LATIN CAPITAL LETTER K
D3 | 0000004C | LATIN CAPITAL LETTER L
D4 | 0000004D | LATIN CAPITAL LETTER M
D5 | 0000004E | LATIN CAPITAL LETTER N
D6 | 0000004F | LATIN CAPITAL LETTER O
D7 | 00000050 | LATIN CAPITAL LETTER P
D8 | 00000051 | LATIN CAPITAL LETTER Q
D9 | 00000052 | LATIN CAPITAL LETTER R
E0 | 00000024 | DOLLAR SIGN
E2 | 00000053 | LATIN CAPITAL LETTER S
E3 | 00000054 | LATIN CAPITAL LETTER T
E4 | 00000055 | LATIN CAPITAL LETTER U
E5 | 00000056 | LATIN CAPITAL LETTER V
E6 | 00000057 | LATIN CAPITAL LETTER W
E7 | 00000058 | LATIN CAPITAL LETTER X
E8 | 00000059 | LATIN CAPITAL LETTER Y
E9 | 0000005A | LATIN CAPITAL LETTER Z
F0 | 00000030 | DIGIT ZERO
F1 | 00000031 | DIGIT ONE
F2 | 00000032 | DIGIT TWO
F3 | 00000033 | DIGIT THREE
F4 | 00000034 | DIGIT FOUR
F5 | 00000035 | DIGIT FIVE
F6 | 00000036 | DIGIT SIX
F7 | 00000037 | DIGIT SEVEN
F8 | 00000038 | DIGIT EIGHT
F9 | 00000039 | DIGIT NINE
FF | 0000009F | APPLICATION PROGRAM COMMAND (APC)

AUTHOR

Copyright (C) 2002-2016 Guido Flohr <<http://www.guido-flohr.net/>>

(<<mailto:guido.flohr@cantanea.com>>), all rights reserved. See the source code for details!`code for details!`

SEE ALSO

Locale::RecodeData(3), Locale::Recode(3), perl(1)

perl v5.34.0

2022-02-06

Locale::RecodeData::IBM281(3pm)