



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

***Rocky Enterprise Linux 9.2 Manual Pages on command 'Locale::RecodeData::IBM904.3pm'***

***\$ man Locale::RecodeData::IBM904.3pm***

Locale::RecodeData::IBM904(3pm)User Contributed Perl DocumentationLocale::RecodeData::IBM904(3pm)

#### NAME

Locale::RecodeData::IBM904 - Conversion routines for IBM904

#### SYNOPSIS

This module is internal to libintl. Do not use directly!

#### DESCRIPTION

This module is generated and contains the conversion tables and routines for IBM904.

#### COMMENTS

The following comments have been extracted from the original charmap:

version: 1.0

source: IBM NLS RM Vol2 SE09-8002-01, March 1990

alias CP904

alias 904

Please note that aliases listed above are not necessarily valid!

#### CHARACTER TABLE

The following table is sorted in the same order as the original charmap. All character

codes are in hexadecimal. Please read 'ISO-10646' as 'ISO-10646-UCS4'.

Local | ISO-10646 | Description

-----+-----+-----		
Local	ISO-10646	Description
00	00000000	NULL (NUL)
01	00000001	START OF HEADING (SOH)
02	00000002	START OF TEXT (STX)
03	00000003	END OF TEXT (ETX)
04	00000004	END OF TRANSMISSION (EOT)
05	00000005	ENQUIRY (ENQ)
06	00000006	ACKNOWLEDGE (ACK)
07	00000007	BELL (BEL)
08	00000008	BACKSPACE (BS)
09	00000009	CHARACTER TABULATION (HT)
0A	0000000A	LINE FEED (LF)
0B	0000000B	LINE TABULATION (VT)
0C	0000000C	FORM FEED (FF)
0D	0000000D	CARRIAGE RETURN (CR)
0E	0000000E	SHIFT OUT (SO)
0F	0000000F	SHIFT IN (SI)
10	00000010	DATALINK ESCAPE (DLE)
11	00000011	DEVICE CONTROL ONE (DC1)
12	00000012	DEVICE CONTROL TWO (DC2)
13	00000013	DEVICE CONTROL THREE (DC3)
14	00000014	DEVICE CONTROL FOUR (DC4)
15	00000015	NEGATIVE ACKNOWLEDGE (NAK)
16	00000016	SYNCHRONOUS IDLE (SYN)
17	00000017	END OF TRANSMISSION BLOCK (ETB)
18	00000018	CANCEL (CAN)
19	00000019	END OF MEDIUM (EM)
1A	0000001A	SUBSTITUTE (SUB)
1B	0000001B	ESCAPE (ESC)
1C	0000001C	FILE SEPARATOR (IS4)

1D | 0000001D | GROUP SEPARATOR (IS3)  
1E | 0000001E | RECORD SEPARATOR (IS2)  
1F | 0000001F | UNIT SEPARATOR (IS1)  
20 | 00000020 | SPACE  
21 | 00000021 | EXCLAMATION MARK  
22 | 00000022 | QUOTATION MARK  
23 | 00000023 | NUMBER SIGN  
24 | 00000024 | DOLLAR SIGN  
25 | 00000025 | PERCENT SIGN  
26 | 00000026 | AMPERSAND  
27 | 00000027 | APOSTROPHE  
28 | 00000028 | LEFT PARENTHESIS  
29 | 00000029 | RIGHT PARENTHESIS  
2A | 0000002A | ASTERISK  
2B | 0000002B | PLUS SIGN  
2C | 0000002C | COMMA  
2D | 0000002D | HYPHEN-MINUS  
2E | 0000002E | FULL STOP  
2F | 0000002F | SOLIDUS  
30 | 00000030 | DIGIT ZERO  
31 | 00000031 | DIGIT ONE  
32 | 00000032 | DIGIT TWO  
33 | 00000033 | DIGIT THREE  
34 | 00000034 | DIGIT FOUR  
35 | 00000035 | DIGIT FIVE  
36 | 00000036 | DIGIT SIX  
37 | 00000037 | DIGIT SEVEN  
38 | 00000038 | DIGIT EIGHT  
39 | 00000039 | DIGIT NINE  
3A | 0000003A | COLON  
3B | 0000003B | SEMICOLON  
3C | 0000003C | LESS-THAN SIGN  
3D | 0000003D | EQUALS SIGN

3E | 0000003E | GREATER-THAN SIGN  
3F | 0000003F | QUESTION MARK  
40 | 00000040 | COMMERCIAL AT  
41 | 00000041 | LATIN CAPITAL LETTER A  
42 | 00000042 | LATIN CAPITAL LETTER B  
43 | 00000043 | LATIN CAPITAL LETTER C  
44 | 00000044 | LATIN CAPITAL LETTER D  
45 | 00000045 | LATIN CAPITAL LETTER E  
46 | 00000046 | LATIN CAPITAL LETTER F  
47 | 00000047 | LATIN CAPITAL LETTER G  
48 | 00000048 | LATIN CAPITAL LETTER H  
49 | 00000049 | LATIN CAPITAL LETTER I  
4A | 0000004A | LATIN CAPITAL LETTER J  
4B | 0000004B | LATIN CAPITAL LETTER K  
4C | 0000004C | LATIN CAPITAL LETTER L  
4D | 0000004D | LATIN CAPITAL LETTER M  
4E | 0000004E | LATIN CAPITAL LETTER N  
4F | 0000004F | LATIN CAPITAL LETTER O  
50 | 00000050 | LATIN CAPITAL LETTER P  
51 | 00000051 | LATIN CAPITAL LETTER Q  
52 | 00000052 | LATIN CAPITAL LETTER R  
53 | 00000053 | LATIN CAPITAL LETTER S  
54 | 00000054 | LATIN CAPITAL LETTER T  
55 | 00000055 | LATIN CAPITAL LETTER U  
56 | 00000056 | LATIN CAPITAL LETTER V  
57 | 00000057 | LATIN CAPITAL LETTER W  
58 | 00000058 | LATIN CAPITAL LETTER X  
59 | 00000059 | LATIN CAPITAL LETTER Y  
5A | 0000005A | LATIN CAPITAL LETTER Z  
5B | 0000005B | LEFT SQUARE BRACKET  
5C | 0000005C | REVERSE SOLIDUS  
5D | 0000005D | RIGHT SQUARE BRACKET  
5E | 0000005E | CIRCUMFLEX ACCENT

5F | 0000005F | LOW LINE  
60 | 00000060 | GRAVE ACCENT  
61 | 00000061 | LATIN SMALL LETTER A  
62 | 00000062 | LATIN SMALL LETTER B  
63 | 00000063 | LATIN SMALL LETTER C  
64 | 00000064 | LATIN SMALL LETTER D  
65 | 00000065 | LATIN SMALL LETTER E  
66 | 00000066 | LATIN SMALL LETTER F  
67 | 00000067 | LATIN SMALL LETTER G  
68 | 00000068 | LATIN SMALL LETTER H  
69 | 00000069 | LATIN SMALL LETTER I  
6A | 0000006A | LATIN SMALL LETTER J  
6B | 0000006B | LATIN SMALL LETTER K  
6C | 0000006C | LATIN SMALL LETTER L  
6D | 0000006D | LATIN SMALL LETTER M  
6E | 0000006E | LATIN SMALL LETTER N  
6F | 0000006F | LATIN SMALL LETTER O  
70 | 00000070 | LATIN SMALL LETTER P  
71 | 00000071 | LATIN SMALL LETTER Q  
72 | 00000072 | LATIN SMALL LETTER R  
73 | 00000073 | LATIN SMALL LETTER S  
74 | 00000074 | LATIN SMALL LETTER T  
75 | 00000075 | LATIN SMALL LETTER U  
76 | 00000076 | LATIN SMALL LETTER V  
77 | 00000077 | LATIN SMALL LETTER W  
78 | 00000078 | LATIN SMALL LETTER X  
79 | 00000079 | LATIN SMALL LETTER Y  
7A | 0000007A | LATIN SMALL LETTER Z  
7B | 0000007B | LEFT CURLY BRACKET  
7C | 0000007C | VERTICAL LINE  
7D | 0000007D | RIGHT CURLY BRACKET  
7E | 0000007E | TILDE  
7F | 0000007F | DELETE (DEL)

80 | 000000A2 | CENT SIGN

FD | 000000AC | NOT SIGN

FE | 000000A6 | BROKEN BAR

#### AUTHOR

Copyright (C) 2002-2016 Guido Flohr <<http://www.guido-flohr.net/>>

(<<mailto:guido.flohr@cantanea.com>>), all rights reserved. See the source code for details!`code for details!`

#### SEE ALSO

Locale::RecodeData(3), Locale::Recode(3), perl(1)

perl v5.34.0

2022-02-06

Locale::RecodeData::IBM904(3pm)